

Online Backup Manager & 1-Click Backup *v5.5*

User's Guide

Blaze Vault Online Backup - Development Department

June 16, 2009

Blaze Vault Online Backup Manager & Blaze Vault 1-Click Backup v5.5

User's Guide

Copyright Notice

The use and copying of this product is subject to a license agreement. Any other use is prohibited. No part of this publication may be reproduced, transmitted, transcribed, stored in a retrieval system or translated into any language in any form by any means without the prior written consent of us. Information in this manual is subject to change without notice and does not represent a commitment on the part of the vendor. We do not warrant that this document is error free. If you find any errors in this document, please report to us in writing.

This product includes softw are developed by the Apache Softw are Foundation (http://www.apache.org/).

Disclaimer

Blaze Vault will not have or accept any liability, obligation or responsibility whatsoever for any loss, destruction or damage (including without limitation consequential loss, destruction or damage) however arising from or in respect of any use or misuse of or reliance on this document. By reading and following the instructions in this document, you agree to accept unconditionally the terms of this Disclaimer and as they may be revised and/or amended from time to time by Blaze Vault without prior notice to you.



Table of Content

1	Over	view	4
	1.1	Benefits	4
	1.2	Features	4
	1.3	Security	5
	1.4	System Requirements	6
2	Instal	lling Blaze Vault	7
	2.1	Installing Blaze Vault for Windows	
	2.2	Installing Blaze Vault for Mac OS X	9
	2.3	Installing Blaze Vault for Linux/Unix/Solaris	11
	2.4	Installing Blaze Vault for Netware	17
3	Unins	stalling Blaze Vault	19
	3.1	Uninstalling Blaze Vault for Windows	
	3.2	Uninstalling Blaze Vault for Mac OS X	
	3.3	Uninstalling Blaze Vault for Linux/Unix/Solaris	
	3.4	Uninstalling Blaze Vault for Netware	
4	Using	g Blaze Vault	
•	4.1	System Tray Launcher (Windows Only)	
	4.2	Logon Dialog	
	4.3	Language Selection	
	4.4	Main Window	
	4.5	User Profile	
	4.6	Backup Logs	
5		ng Up Backup Sets	
5		Backup Set Type	
	5.1 5.2	• • • •	
		Backup Source	
	5.3 5.4	•	
	5.5	Continuous Data Protection (CDP) Encryption	
	5.6	Mapped Network Drive	
	5.7	Backup Filter	
	5.8	Pre/Post-Backup Command	
	5.9	Temporary directory	
	5.10	Transfer Block Size	
	5.10	Follow Symbolic Link (Linux/Unix/Mac only)	
	5.12	Microsoft's Volume Shadow Copy Service (VSS)	
	5.13	Retention Policy	
	5.14	Extra Backup (Off-Line backup, Logout Reminder).	
	5.15	In-File Delta	
	5.16	Local Copy	
	5.17	Using One Backup Account for Multiple Computers	
6		ing Up Files	
U			
	6.1 6.2	How files are backed up	
	6.3	Backup files directly to the backup server	
7			
7		oring Files	
	7.1	Restore backup files directly from backup server	
	7.2	Restore backup files from removable hard disk	
	7.3	IP addresses Restriction for Online Restore	62



8	In-File	e Delta Technology	64
	8.1	Overview	64
	8.2	Block Size	67
	8.3	Minimum File Size	
	8.4	Up loading full file again	
	8.5	Advanced In-file delta type	
9	Backu	ıp/Restore Oracle 8i / 9i / 10g / 11g	
	9.1	Requirements	
	9.2	Overview	
	9.3	How to backup an Oracle Database (Physical Backup)	
	9.4	How to restore an Oracle Database	
	9.5	How to restore a single tablespace.	
10	9.6	Export and Import a Database (Logical Backup)	
10	10.1	np/Restore Microsoft SQL Server 7.0 / 2000 / 2005 / 2008	
	10.1	Overview	
	10.2	How to backup Microsoft SQL Server database(s)	
	10.4	How to restore Microsoft SQL Server database(s)	
11		p/Restore Lotus Domino / Notes	
11	11.1	Requirements	
	11.1	Overview	
	11.3	How to backup Lotus Domino / Notes database(s) / file(s) on Windows	
	11.4	How to restore Lotus Domino / Notes database(s) / file(s) on Windows	
	11.5	How to backup Lotus Domino / Notes database(s) / file(s) on Linux	
	11.6	How to restore Lotus Domino / Notes database(s) / file(s) on Linux	
12	Backup/Restore Microsoft Exchange Server		
	12.1	Requirements	
	12.2	Overview	
	12.3	How to backup Microsoft Exchange Server	110
	12.4	How to restore Microsoft Exchange Server	113
13	Backu	np/Restore Windows System State	117
	13.1	Requirements	117
	13.2	Overview	117
	13.3	How to backup Windows System State	
	13.4	How to restore Windows System State	120
14	Backu	np/Restore Individual Brick Level Backup for Microsoft Exchange Server	121
	14.1	Requirements	
	14.2	Overview	
	14.3	Granting Privileges	
	14.4	How to backup Individual Brick Level Backup	
	14.5	How to restore Individual Brick Level Backup	
15		np/Restore System with Microsoft Windows System Backup	
	15.1	Requirements	
	15.2	Overview	
	15.3	How to backup system with Microsoft Windows System Backup	
1.6	15.4	How to restore system with Microsoft Windows System Backup	
16		np/Restore Windows System with ShadowProtect	
	16.1	Requirements	
	16.2 16.3	Overview	
	16.3	How to restore system with ShadowProtect	
	10.4	110 w to restore system with shadowr forcet	149



17	Rackur	o/Restore MySQL Server	155
1 /	_	•	
	17.1	Requirements	
	17.2	Overview	
	17.3	How to backup MySQL server on Windows	155
	17.4	How to backup MySQL server on Linux (command line mode)	158
	17.5	How to restore MySQL server	159
18	Email F	Reporting	161
	18.1	New User Report	161
	18.2	Forgot Password Report	
	18.3	Backup Job Report	163
	18.4	Setting Change Report	166
	18.5	Inactive User Reminder	
19	Web F	eatures	168
	19.1	Install Blaze Vault	168
	19.2	Update User Profile	168
	19.3	Request Forgotten Password	
	19.4	Restore/Delete/Undelete Backup Files	170
	19.5	Review Backup Jobs	171
	19.6	Review Storage Statistics	173
20	Further	· Information	174
	20.1	FAQs	174
	20.2	Contact Us	174



1 Overview

1.1 Benefits

- Easy Backup of
 - 1. Microsoft Exchange Server 2000 / 2003 / 2007
 - Microsoft SQL Server 7.0 / 2000 / 2005 / 2008
 - 3. Lotus Domino/Notes 5.0 or above
 - 4. Oracle 8i or above
 - 5. MySQL 3.2.4 or above
 - 6. Windows System State for Windows 2000 / XP / 2003
 - (New in 5.5.3.0) Windows Complete System Backup for Windows 2008 and Windows Vista Business / Enterprise / Ultimate edition
 - 8. (New in 5.5.3.0) Bare metal backup using StorageCraft ShadowProtect
 - 9. Outlook and Outlook Express (i.e. *.pst, *.dbx and *.wab)
 - 10. Important personal settings, e.g. Desktop, Favorite, My Documents and History etc
 - 11. Other common files (e.g. *.doc, *.xls)
- Support backing up only changes within a file (using in-file delta technology)
- Support backing up of open files on Windows XP/2003/Vista (Volume Shadow Copy)
- Support backing up of Windows NTFS access privileges, Linux access privileges and modes, Mac
 OS X metadata and resource forks
- Easy to use, deploy and maintain

1.2 Features

- (New in 5.5.1.0) Re-design of Blaze Vault / Blaze Vault 1-Click GUI
- (New in 5.5.1.0) Continuous data protection start backup whenever a file is being modified
- (New in 5.5.1.0) Add options for user to choose to backup using 256-bit Encryption
- (New in 5.5.1.0) Add the functionality of "Backup and Sleep (Hibernate)" and "Backup and standby"
- (New in 5.5.1.0) Allow backup schedule to run every X minutes
- Full support of Microsoft Exchange individual email, contacts, calendars, tasks etc.
- Choose whether to restore "file permissions" during restore.
- For "Local Copy" backup, ability to choose whether to perform a local copy backup only and skip the
 offsite backup.
- Lotus Notes/Domino agent for Linux.
- Auto Upgrade Agent to automatically upgrade the client software.
- User configurable incremental / differential in-file delta backup mode (i.e. backing up only changes within a file since the last incremental or full backup according to each user's preference).
- Allow in-file delta backup mode to be overridden by each user individually according to backup time (e.g. enforcing full (or incremental or differential) backup of all files every Sunday or the 1st day of every month).
- Volume Shadow Copy backup (i.e. backing up files even when they are exclusively open, e.g. Outlook.pst).
- In-File Delta backup (i.e. backing up only changes within files).
- Off-line backup mode and logout backup reminder.
- Customizable backup schedule allows backups to be scheduled at any time.
- Compress and encrypt data automatically before sending them to the server (server stores only encrypted data).
- Increment backup strategy ensures that only new or updated files are sent to the backup server.
- Support both full backup (database backup) and incremental backup (transaction log backup) for Microsoft SQL Server 7.0/2000, Microsoft Exchange Server 2000/2003, Lotus Domino/Notes 5.0 and Oracle 8i or above.
- Can integrate with external "Open File Manager" to provide open file backup support to all open files.



- Access backup data anytime, anywhere by using a web browser.
- Comprehensive backup report lists all files backed up. Backup report delivered automatically via email.
- Backup data are CRC validated before they are stored on server.
- Fully user customizable data retention policy allows users to have access to deleted files using the least possible storage space on the backup server.
- Can select source backup files easily by using a backup filter, e.g. selecting all *.doc and *.xls in your computer in a single operation.
- Run any custom OS commands before/after a backup job.
- Run on Windows, Mac OS X, Linux, NetWare, Unix and all other platforms supporting a Java2 Runtime Environment.
- Periodic backup files validation on backup server ensures backup files are 100% valid and fully restorable when needed.

1.3 Security

- 128-bit point-to-point SSL communication between server and client
- Support HTTP/HTTPS Proxy and Socks v4/v5 firewall
- Data are 128-bit/256-bit encrypted when stored on the backup server
- Choice of different encryption algorithms, e.g. Twofish, Triple DES, Advanced Encryption Standard (AES)
- Choice of different encryption modes, e.g. Electronic Cook Book (ECB) and Cipher Block Chaining (CBC)
- An random initializing vector, salt and iteration count will be generated by the software automatically for each file when encrypting your data
- Each backup user can restrict online access to his files to his pre-defined list of IP addresses



1.4 System Requirements

Client-side applications			
	Supported Platforms	Application Compatibilities	Hardware Requirements
Blaze Vault	 Windows 95 / 98 / ME / NT / 2000 / XP / 2003 / Vista / 2008 Linux kernel 2.4 or above NetWare 5.2 or above Solaris 2.x or above AIX HP-UX FreeBSD Mac OS X 10.3 or above All other operating systems that supports Java2 Runtime Environment 1.4.2 or above 	 Microsoft Exchange Server 2000 / 2003 / 2007 Microsoft SQL Server 7.0 / 2000 / 2005 / 2008 Lotus Domino / Lotus Notes 5.0 or above Oracle 8i or above MySQL 3.2.4 or above Outlook / Outlook Express i.e. *.pst, *.dbx and *.wab Other common files e.g. *.doc, *.xls Also supports backing up of: Windows System State (all platforms except Vista / 2008) Windows System Backup for Vista / 2008 Windows NTFS access privileges Linux access privileges and modes Mac OS X metadata and resource forks 	Memory: 128MB (minimum) 256MB (recommended) Disk Space: 110MB Network Protocol: TCP/IP (http/https)
Blaze Vault 1-Click	 Windows 2000 / XP / 2003 / Vista / 2008 Mac OS X 10.3 or above 	 Outlook / Outlook Express i.e. *.pst, *.dbx and *.wab Other common files e.g. *.doc, *.xls Also supports backing up of: Windows NTFS access privileges 	Memory: 128MB (minimum) 256MB (recommended) Disk Space: 110MB Network Protocol: TCP/IP (http/https)



2 Installing Blaze Vault

Before you can start backing up data to the Ahsay Offsite Backup Server (Blaze Vault Server), you need to install the Ahsay Online Backup Manager (Blaze Vault) onto your computer.

2.1 Installing Blaze Vault for Windows

1. Download the Blaze Vault installer (obm-win.zip) from the website.



- 2. Follow the instructions on the installation wizard to complete installation
- When finished, a new icon (Blaze Vault / Blaze Vault 1-Click) will be installed to the system tray (near the clock) automatically and Blaze Vault / Blaze Vault 1-Click will be launched automatically.
- 4. (optional) Enter the backup server host name in the [Address] field and press the [Next] button.
- 5. If you don't have a backup account, register a trial user by the following steps:
 - i. Enter the [Login Name], [Password] and [Confirm Password] of your choice
 - ii. Enter your [Email] in the text field provided
 - iii. Press the [Submit] button
 - iv. You should be logged to the backup server already (if the [Login Name] of your choice is already taken by another user, try a different login name)
- 6. If you have a backup account already, select [already a user?] and logon to the server with your existing username and password.
- 7. If this is your first time logging into the server, you will be guided to create a backup set:
 - i. Enter a backup set name of your choice in the [Name] field and choose the type of backup set in the [Type] field
 - ii. Select the files that you want to backup
 - iii. Setup the backup schedule by pressing the [Add] button (please note that you can add




- multiple backup schedules to a backup set and please select the "Run scheduled backup on this computer" checkbox if you would like to run Continuous Data Protection (CDP))
- iv. Setup the encryption setting for your backup set (if you don't know much about encryption, just accept the default values here)
- v. Press the [OK] button to complete the configuration of backup set Scheduled backup will run automatically if you leave your computer on.
- 8. To run a backup immediately, click [Backup] button on the left panel, select the backup set and press [OK] button.
- 9. Setup completed.



2.2 Installing Blaze Vault for Mac OS X

1. Download the Blaze Vault installer (obm-mac.zip) from the website.



- 2. Expand the archive and run the installation wizard [Blaze Vault / Blaze Vault 1-Click] within the archive.
- 3. Restart your Mac. Double click the desktop Blaze Vault / Blaze Vault 1-Click icon to start.
- 4. (optional) Enter the backup server host name in the [Address] field and press the [Next] button.
- 5. If you don't have a backup account, register a trial user by the following steps:
 - i. Enter the [Login Name], [Password] and [Confirm Password] of your choice
 - ii. Enter your [Email] in the text field provided
 - iii. Press the [Submit] button
 - iv. You should be logged to the backup server already (if the [Login Name] of your choice is already taken by another user, try a different login name)
- 6. If you have a backup account already, select [already a user?] and logon to the server with your existing username and password.
- 7. If this is your first time logging into the server, you will be guided to create a backup set:
 - Setup the backup schedule by pressing the [Add] button (please note that you can add multiple backup schedules to a backup set and please select the "Run scheduled backup on this computer" checkbox if you would like to run Continuous Data Protection (CDP))
 - Setup the encryption setting for your backup set (if you don't know much about encryption, just accept the default values here)
 - iii. Press the [OK] button to complete the configuration of backup set

Scheduled backup will run automatically if you leave your computer on.

8. To run a backup immediately, click [Backup] button on the left panel, select the backup set and




9. Setup completed.



2.3 Installing Blaze Vault for Linux/Unix/Solaris

Linux

1. Download the Blaze Vault tarball release (obm-nix.tar.gz) from the website.



- 2. Unpack the install file to /usr/local/obm
 - # mkdir /usr/local/obm
 - # cd /usr/local/obm
 - # gunzip obm-nix.tar.gz
 - # tar -xf obm-nix.tar
- 3. Install Blaze Vault
 - # ./bin/install.sh >install.log

All installation information can be found in the file "install.log"


The backup scheduler and autoupgrade services are automatically installed. Backup sets can now run at their scheduled times automatically. \ast

4. Please go to X Window or command line mode to continue installation.



Solaris

1. Download the Blaze Vault tarball release (obm-nix.tar.gz) from the website.



- 2. Unpack the install file to /usr/local/obm
 - # mkdir /usr/local/obm
 - # cd /usr/local/obm
 - # gunzip obm-nix.tar.gz
 - # tar -xf obm-nix.tar
- 3. Remove bundled jvm
 - # rm -rf /usr/local/obm/jvm
- 4. Install J2SE Java Runtime Environment (JRE) 1.4.x or later to /usr/java
- 5. Create a symbolic link for JRE
 - # In -s /usr/java /usr/local/obm/jvm
- 6. Set the JAVA_HOME environment variable
 - # JAVA_HOME=/usr/java; export JAVA_HOME
- 7. Install Blaze Vault
 - # ./bin/install.sh >install.log

All installation information can be found in the file "install.log"




The backup scheduler and autoupgrade services are automatically installed. Backup sets can now run at their scheduled times automatically. *

8. Please go to X Window or command line mode to continue installation.

BSD

1. Download the Blaze Vault tarball release (obm-nix.tar.gz) from the website.



- 2. Unpack the install file to /usr/local/obm
 - # mkdir /usr/local/obm
 - # cd /usr/local/obm
 - # gunzip obm-nix.tar.gz
 - # tar -xf obm-nix.tar
- 3. Remove bundled jvm
 - # rm -rf /usr/local/obm/jvm
- 4. Download J2SE Java Runtime Environment (JRE) 1.4.x or later

Depending on your platform and BSD release, download the corresponding JRE and dependant packages. For example, we are using FreeBSD 6.1 i386 for installation:

Download javavmwrapper-2.3.tbz and diablo-jre-freebsd5.i386.1.5.0.07.01.tbz in the following links.

http://www.freebsd-fr.org/ports/java.html#javavmwrapper-2.3

http://www.freebsdfoundation.org/downloads/java.shtml

http://www.freebsd.org/ports/java.html#diablo-jre-1.5.0.07.01 3 (See package dependancy of



your machine)

Install J2SE Java Runtime Environment (JRE) 1.4.x or later to /usr/local/diablo-jre1.5.0

Use following command to install package # pkg_add javavmwrapper-2.3.tbz # pkg_add diablo-jre-freebsd5.i386.1.5.0.07.01.tbz

6. Create a symbolic link for JRE

In -s /usr/local/diablo-jre1.5.0 /usr/local/obm/jvm

If you are using csh as your shell, you need to type "rehash" and hit enter to make the symbolic link take effect. For other shell types it should work.

setenv JAVA_HOME /usr/local/obm/jvm

7. Verify the installed JRE

\$JAVA_HOME/bin/java -version

See if the output does not contain warning

With warning

Java HotSpot(TM) Client VM warning: Can't detect initial thread stack location java version "1.4.2_12"
Java(TM) 2 Runtime Environment, Standard Edition (build 1.4.2_12-b03)
Java HotSpot(TM) Client VM (build 1.4.2_12-b03, mixed mode)

Without warning

java version "1.5.0"
Java(TM) 2 Runtime Environment, Standard Edition (build diablo-1.5.0-b01)
Java HotSpot(TM) Client VM (build diablo-1.5.0_07-b01, mixed mode)

- 8. Install Blaze Vault
 - # ./bin/install.sh >install.log

All installation information can be found in the file "install.log"

9. Install the backup scheduler and autoupgrade services

Add two entries to system file /etc/rc.conf for auto starting backup scheduler and autoupgrade agent.

```
# obmaua_enable="YES"
# obmscheduler_enable="YES"
```

Restart computer or run the following scripts

```
# /usr/local/etc/rc.d/obmscheduler start &
# /usr/local/etc/rc.d/obmaua start &
```

The backup scheduler and autoupgrade services are automatically installed. Backup sets can now run at their scheduled times automatically. *

10. Please go to X Window or command line mode to continue installation.

X-Windows

1. Set the DISPLAY environment variables



Linux / Unix (sh, bash): DISPLAY=IP_ADDRESS_OF_XTERMINAL[:0.0]; export DISPLAY

For example

DISPLAY=:0.0; export DISPLAY or DISPLAY=127.0.0.1; export DISPLAY or DISPLAY=127.0.0.1:0.0; export DISPLAY or DISPLAY=192.168.0.2; export DISPLAY or DISPLAY=192.168.0.2:0.0; export DISPLAY

BSD (csh): setenv DISPLAY IP_ADDRESS_OF_XTERMINAL[:0.0]

For example

setenv DISPLAY:0.0 or setenv DISPLAY 127.0.0.1 or setenv DISPLAY 127.0.0.1:0.0 or setenv DISPLAY 192.168.0.2 or setenv DISPLAY 192.168.0.2:0.0

2. Run Blaze Vault Online Backup Manager

sh /usr/local/obm/bin/RunOBC.sh &

- 3. (Optional) Enter the backup server host name in the [Address] field and press the [Next] button.
- 4. If you don't have a backup account, register a trial user by the following steps:
 - i. Enter the [Login Name], [Password] and [Confirm Password] of your choice
 - ii. Enter your [Email] in the text field provided
 - iii. Press the [Submit] button
 - iv. You should be logged to the backup server already (if the [Login Name] of your choice is already taken by another user, try a different login name)
- 5. If you have a backup account already, select [already a user?] and logon to the server with your existing username and password.
- 6. If this is your first time logging into the server, you will be guided to create a backup set
 - Enter a backup set name of your choice in the [Name] field and choose the type of backup set in the [Type] field
 - ii. Select the files that you want to backup
 - iii. Setup the backup schedule by pressing the [Add] button (please note that you can add multiple backup schedules to a backup set and please select the "Run scheduled backup on this computer" checkbox if you would like to run Continuous Data Protection (CDP))
 - Setup the encryption setting for your backup set (if you don't know much about encryption, just accept the default values here)
 - v. Press the [OK] button to complete the configuration of backup set
- 7. To run a backup immediately, click [Backup] button on the left panel, select the backup set and press [OK] button.
- 8. Setup completed.

Command Line Mode

- 1. Use the web interface to add, update and remove backup sets
 - i. If you want to update a backup set, make changes to a backup set and press the [Update] button Enter your [Email] in the text field provided
 - ii. If you want to add a new backup set, click the [Add] link
 - iii. If you want to remove a backup set, Select the backup set to be remove and click the [Remove] link



2. Using Backup Configurator

sh /usr/local/obm/bin/Configurator.sh

3. Enter your Login Name, Password, Backup Server URL and proxy setting as shown below

4. If you have created a new backup set using the web interface, you set the encrypting key, the encrypting algorithm and the encrypting mode of this backup set by following instructions below.

Important: You cannot change these parameters once they are set

Found new backup set 'xxx'
Please enter the following values for this backup set:

Encrypting Algorithm?
(1) Twofish (2) AES (3) Triple DES (4) No encryption: 1
Encrypting Key: **************
Re-Enter Encrypting Key: *************
Encrypting Mode? (1) ECB (2) CBC: 1
Run scheduled backup on this computer? (Y)es or (N)o: Y

5. If you want to make any changes to the setting above, you can use the main menu below to do so.

Main Menu:

.____

- (1). List Backup Setting
- (2). Change Password
- (3). Change Network Setting
- (4). Change run scheduled backup setting
- (5). Toggle Masked Field (Password, Encryption Key)
- (6). Generate Configuration Report (text format)
- (7). Quit

Your Choice:

6. You can then run a backup by executing the command below.

sh /usr/local/obm/bin/RunBackupSet.sh [BACKUP_SET]

where [BACKUP_SET] is the name of backup set to be run


7. Setup completed.

^{*} The backup scheduler and autoupgrade services are verified to install successfully on Solaris, FreeBSD and all major Linux distributions. If these services for other platforms cannot be installed, please refer to the specific OS manual for further information.



2.4 Installing Blaze Vault for Netware

1. Download the Blaze Vault zip release (obm-netware.zip) from the website.



- 2. Expand the zip file to SYS:\Blaze Vault
- 3. Install Blaze Vault

SYS:\> SYS:\OBM\aua\bin\install-aua.ncf

4. Start Auto Upgrade Agent

SYS:\> SYS:\OBM\aua\bin\startup.ncf

5. If you want scheduled backup to run automatically, you must start the backup scheduler by

SYS:\> SYS:\OBM\bin\Scheduler.ncf

All backup sets will now be run at their scheduled times automatically.

- 6. Open Blaze Vault by running SYS:\Blaze Vault\bin\RunBackupManager.ncf
- 7. (Optional) Enter the backup server host name in the [Address] field and press the [Next] button.
- 8. If you don't have a backup account, register a trial user by the following steps:
 - i. Enter the [Login Name], [Password] and [Confirm Password] of your choice
 - ii. Enter your [Email] in the text field provided
 - iii. Press the [Submit] button
 - iv. You should be logged to the backup server already (if the [Login Name] of your choice is already taken by another user, try a different login name)
- 9. If you have a backup account already, select [already a user?] and logon to the server with your



existing username and password.

- 10. If this is your first time logging into the server, you will be guided to create a backup set
 - i. Enter a backup set name of your choice in the [Name] field and choose the type of backup set in the [Type] field
 - ii. Select the files that you want to backup
 - iii. Setup the backup schedule by pressing the [Add] button (please note that you can add multiple backup schedules to a backup set and please select the "Run scheduled backup on this computer" checkbox if you would like to run Continuous Data Protection (CDP))
 - iv. Setup the encryption setting for your backup set (if you don't know much about encryption, just accept the default values here)
 - v. Press the [OK] button to complete the configuration of backup set
- 11. To run a backup immediately, click [Backup] button on the left panel, select the backup set and press [OK] button.
- 12. Setup completed.



3 Uninstalling Blaze Vault

This section describes the steps required to uninstall Blaze Vault from your computer.

3.1 Uninstalling Blaze Vault for Windows

- 1. Open [Start] -> [Control Panel] -> [Add/Remove Programs]
- 2. Select [Blaze Vault Online Backup Manager] from the list and press the [Remove] button

3.2 Uninstalling Blaze Vault for Mac OS X

1. Remove all program files by running

```
# cd $OBM_HOME/bin
# sudo ./uninstall.sh
```

2. Remove all backup setting by removing ~/.obm

```
# rm -rf ~/.obm
```

3. Restart your computer

3.3 Uninstalling Blaze Vault for Linux/Unix/Solaris

1. Run the uninstall scripts

```
# sh /usr/local/obm/bin/uninstall.sh
```

Removing Scheduler from service using script name obmscheduler Using init script path /etc/init.d
Using run level script path /etc/rc.d
Removing symbolic link from run levels
Removing script file obmscheduler from /etc/init.d
Shutting down AutoUpdateAgent
Waiting 5 seconds for AutoUpdateAgent to clean up
Removing AutoUpdateAgent from service using script name
Using init script path /etc/init.d
Using run level script path /etc/rc.d
Removing symbolic link from run levels
Removing script file obmaua from /etc/init.d
Online Backup Manager uninstall service is complete!
It is now safe to remove files from /usr/local/obm

2. Remove installed files and all application data

```
#rm -rf /usr/local/obm
#rm -rf ~/.obm
```

3. Uninstall completed.

3.4 Uninstalling Blaze Vault for Netware

1. Stop the running backup scheduler by running

SYS:\> touch SYS:\OBM\ipc\Scheduler\stop



2. Stop the running auto upgrade agent by running

SYS:\> SYS:\OBM\aua\bin\shutdown.ncf

- 3. Remove all program files by removing the directory SYS:\OBM
- 4. Remove all backup settings by removing the directory SYS:\.OBM



4 Using Blaze Vault

This chapter will describe all the features available in Blaze Vault and outline how you can use Blaze Vault to meet various backup needs.

4.1 System Tray Launcher (Windows Only)

After you have successfully installed Blaze Vault onto your computer, an Blaze Vault icon will be added to the system tray area (next to your system clock) automatically.



This icon is the entry point to Blaze Vault. Right clicking the icon will show a menu that provides the following functions:

Menu Item	What it does
Open	Run Blaze Vault.
Backup	Runs a specific backup set (or all backup sets) chosen from the submenu in silent background mode.
Backup and Logoff	Runs a specific backup set (or all backup sets) chosen from the submenu in silent background mode and then logoff from Windows when finished.
Backup and Restart	Runs a specific backup set (or all backup sets) chosen from the submenu in silent background mode and restart Windows when finished.
Backup and Shutdown	Runs a specific backup set (or all backup sets) chosen from the submenu in silent background mode and shutdown the computer when finished.
Backup and Standby	Runs a specific backup set (or all backup sets) chosen from the submenu in silent background mode and enter the Standby mode of Windows.
Backup and Hibernate	Runs a specific backup set (or all backup sets) chosen from the submenu in silent background mode and enter the Hibernate mode of Windows.
Help	Shows a help dialog
Stop running backup	Interrupts a running backup set (or all backup sets) chosen from the sub-menu.
Exit	Close this system tray launcher application.



4.2 Logon Dialog

Before you can use Blaze Vault, you have to be authenticated by Blaze Vault Server first. The logon dialog shown below will check if you have the right to access Blaze Vault by submitting the username and password you provided to the backup server.



For secure communication, you can choose to communicate with Blaze Vault Server in SSL (Secure Socket Layer) by selecting the [https] option.

The [Address] field shows the network address of Blaze Vault Server to which Blaze Vault will connect to authenticate your username and password. You can use either a resolvable host name (e.g. backup.yourdomain.com) or an IP address (e.g. 192.168.1.1).


If Blaze Vault Server is not accepting connection from the standard ports (Port 80 and 443 for http and https respectively), you can append a semi-colon ":" and the custom port number to the host name of the [Address] field (e.g. www.backup-provider.com:8080) to connect to the server using the custom port number (port 8080 in this case).

If you need to connect to the server through proxy, just enter your proxy setting in the [Proxy Setting] section. For [SOCKS] proxy, both v4 and v5 without user authentication are supported.



4.3 Language Selection


You can switch the language of the Blaze Vault user interface by choosing the desired language available from the [Language] drop down list. The languages available includes English, Czech, Danish, Dutch, French, Spanish, Portuguese, Icelandic, Norwegian, Finnish, Italian, German, Swedish, Chinese (Traditional and Simplified), Japanese, Lithuanian and Slovenian.



4.4 Main Window


Press [OK] to logon. After the backup server authenticates you successfully, the Blaze Vault main window appears.





4.5 User Profile

You can then use Blaze Vault to update your user profile. Press the button to open the [User Profile] dialog.



You can perform the following update to your user profile.

To change your [Display Name], enter the new display name in the [Display Name] field and press [OK].




To change your [Password], press the [Change] button next to the password field. A [Change Password] dialog will appear. Enter your original password and new password into the text field of this dialog and press [OK].



To change your [Time Zone], just select your time zone from the drop down list next to the time zone entry.

To add a new contact email to this account, press the [Add] button in the [Contact] section. A [Add New Contact] dialog will appear. Enter a name and an email address in the text field provided and then press the [OK] button.



To remove a contact email, select the email that is to be removed from the email list and press the [Remove] button. Press [OK] to confirm the removal.

To update a contact email, select the email that is to be updated from the email list and press the [Properties] button. A [Properties] dialog will appear. After you have made the changes that you want, press the [OK] button.



4.6 Backup Logs


All backup activities are logged to backup activity log files. They are available for reviewing from Blaze Vault.

How to review backup activities?

You can review all your backup Jobs by

- 1. Press the [Backup Log] button on the Blaze Vault main window.
- 2. Select the Backup Set you want to review from the [Backup Set] drop down list.
- 3. Select the Backup Job you want to review from the [Log] drop down list.








5 Setting Up Backup Sets

A backup set contains all backup settings of a backup operation. This section will describe all features available within a backup set and explain how you can use each of them to achieve various tasks.


Each backup account can have multiple backup sets. Each backup set is an individual and independent entity. For example, if you want one directory to be backed up during the day and another directory to be backed up during the night, you can create two backup sets, each with a different backup schedule and backup source, to serve this need.

To start setting up backup sets, click the button to open the [Backup Setting] dialog. As an example, let's create a "File Backup Set" for the rest of this chapter.



On the left panel, press the 🗈 button to create a new backup set.

5.1 Backup Set Type





A backup set can be of one of the following types:

Backup Type	Description
File	Backup set type to backup common files/directories
Lotus Domino Server	Backup set type to backup Lotus Domino
Lotus Notes Client	Backup set type to backup Lotus Notes
MS Exchange Server	Backup set type to backup Microsoft Exchange Server 2000 / 2003 / 2007
MS Exchange Mail Level	Backup set type to backup individual emails, contacts, calendars, tasks etceteras from Microsoft Exchange Server 2000 / 2003 /2007
MS SQL Server	Backup set type to backup Microsoft SQL Server 7.0 / 2000 / 2005
MySQL Server	Backup set type to backup MySQL Server
Oracle Database Server	Backup set type to backup Oracle 8i/9i/10g database
System State	Backup set type to backup Microsoft Window's System State

Backup set type is defined at backup set creation and cannot be modified. If you want to change the backup set type, you have to create another backup set in the new backup set type.

5.2 Backup Source

A "Backup Source" defines the files/directories that are to be included in a backup set. There are two types of backup source: Selected and Deselected. Selected backup source defines files/directories that are to be included in a backup set while deselected backup source defines files/directories that are to be excluded from a backup set. Blaze Vault will generate appropriate backup source setting for you automatically when you make your backup source selection.

Please note that for Windows operating systems, if the "Hide protected operating files (Recommended)" setting is enabled for the file explorer, system folders/files will not be shown in the backup source. By selecting the parent folders however, all subfolders (including system folders/files) will be included in the backup set. Thus if you want to exclude system folders (e.g. recycle bin) from the backup, please select the desired folders/files directly rather than selecting the parent folder. Alternatively, you can enter the corresponding system path to the [Exclude List] of the backup set using the web interface.


On the first screen of the dialog, you can easily select the following common folders to be backed up:

- 1. "Desktop" folder
- 2. "My Documents" folder
- 3. "Favorites" folder
- 4. "Outlook" and "Outlook Express" mail store folder





On clicking the [Advanced] button, you can easily select other common folders to be backed up as well.



The checkbox next to the files/directories shown above can be in one of the following mode:

Mode	Description	
>	All files/directories (recursively) under this directory will be backed up	
>	All files/directories (recursively), except those explicitly excluded, under this directory will be backed up. If you add files/directories to this directory in the future, they will be backed up as well.	
	Only the checked files/directories under this directory will be backed up. If you add files/directories to this directory in the future, they will NOT be backed up.	
	Nothing under this directory will be backed up.	

By clicking on the boxes, you can change the modes of each file/directory, in order to create a set of files to be backed up.




You can change the backup source anytime after creating the backup set, by clicking the [Backup Source] node of the left panel on the [Backup Setting] dialog.



5.3 Backup Schedule

A "Backup Schedule" defines the frequency and the time that backups should run automatically.



Backup schedule can be in one of the following types:

Туре	Description	
Daily	Backup Jobs will run everyday	
Weekly	Backup Jobs will run on the specified day(s) of every week	
Monthl y	Backup Jobs will run on the specified day or on a day with a given criteria (e.g. first weekend, last weekday) of every month	
Custo m	Backup job will run once on any particular date	

For each schedule type above, backup will run at the scheduled time for a maximum of the duration specified (or until all data are backed up if [Stop on backup completion] option is chosen). If a backup job does not finish within the maximum duration specified, it will be interrupted.

Please note that you can have more than one schedule within a backup set. For example, you can have a daily backup schedule that runs at 13:00 at noon and another daily backup schedule that runs at 00:00 at midnight. The combination of these schedules effectively creates a backup schedule that runs daily at 00:00 and 13:00 everyday.

You can change the backup schedules anytime after creating the backup set, by clicking the [Backup Schedule] node of the left panel on the [Backup Setting] dialog.

5.4 Continuous Data Protection (CDP)


Blaze Vault / Blaze Vault 1-Click Continuous Data Protection (CDP) feature enables files to be backed automatically at the time when there are changes to files on local hard disks. The benefits of using CDP are:

- All intra-day interim changes are backed up automatically. Even if the computer breaks down completely before users had the change to backup their data at the end of the day in logout backup reminder, all changes within the day have been backed up safely by CDP and no data are lost.
- 2. Sometimes users do not save their data in the folders designated as backup source path and thus results in data not being backed up even when backup runs. Since CDP tracks all changes of files on local hard disk automatically for users, all files changed by the users are automatically backed up no matter whether the files are located in the backup source paths or not. This makes defining a



backup set a much easier task for both administrators and users.

Although CDP is a very helpful feature, it does have some drawbacks. For example, a memory resident program, which tracks file changes to the file system and backs up files continuously in background, consumes both a computer's CPU and memory resources. It can potentially slow down a computer considerably. For application servers, e.g. Microsoft Exchange Server or Microsoft SQL Server, that does not require CDP features (you can use transaction log backup interval of as frequent as every 1 minute to mimic a continuous backup strategy instead), please turn off CDP by changing the startup method of [Control Panel] -> [Administrative Tools] -> [Services] -> [Continuous Data Protection (Blaze Vault)] -> [General] -> [Startup type] to "manual".



The following table explains all CDP parameters available within a backup set.


Parameter	Description
Enable Continuous Data Protection (local disk only)	It defines whether CDP is enabled in this backup set. Please note that CDP will only backup files on local hard disks, not files on floppy drives, removable drives and network mapped drives.
Time Mark Interval	It defines the interval of point-in-time views generated by CDP. For example, if this setting is set to "60 minutes", the point-in-time views selectable under Blaze Vault / Blaze Vault 1-Click restore wizard and Blaze Vault Server File Explorer will be "00:00", "01:00", "02:00" etc, for each day.
Minimum Update Interval	It defines the minimum interval that repeatedly updated files are backed up again. For example, if a file is updated every minute and the [Minimum Update Interval] is set to "10 minutes", CDP backs up this file every 10 minutes instead of every minute. If you want all changes to be backed up instead, please change this setting to "Always". However, since Blaze Vault Server keeps only 1 snapshot of file within a single point-in-time view ("Time Mark Interval"), only the last backup file within each point-in-time view is restorable from Blaze Vault Server, all other interim backup files are overwritten automatically without notice. Please note that this applies to all full file backup only, but not for files that are backed up incrementally by in-file delta. To maintain a valid in-file delta chain for incremental delta files, Blaze Vault Server will not delete



	incremental delta files automatically. If you are interested in restoring any of these snapshots backed up, you can use the [Show all files] view to display all interim incremental backup files.
Туре	[Backup file(s) selected by backup sources and filters] – when this option is selected, CDP will only back up all changed files selected by backup set sources and filters settings [Backup all files] – when this option is selected, CDP will only back up all changed files [Custom] – when this option is selected, CDP will only back up changed files selected by CDP backup sources and CDP backup filters settings
Do not backup files defined as system files	If this option is enabled, CDP will exclude the following files from its backup:
	1. '[WINDOWS_DIR]' (e.g. C:\WINDOWS*) 2. '[PROGRAM_DIR]' (e.g. C:\Program Files*) 3. '[RECYCLE_BIN_DIR]' (e.g. C:\RECYCLER, D:\\$Recycle.Bin) 4. '[ALL_LOCAL_DRIVE]:\Pagefile.sys' (e.g. C:\Pagefile.sys, D:\Pagefile.sys) 5. '[ALL_LOCAL_DRIVE]:\hiberfil.sys' (e.g. C:\hiberfil.sys, D:\hiberfil.sys) 6. '[ALL_LOCAL_DRIVE]:****.tmp' (e.g. C:\xxx\abc.tmp, D:\yyy\abc.tmp) 7. '[ALL_LOCAL_DRIVE]:\System Volume Information' (e.g. C:\System Volume Information, D:\System Volume Information) 8. '[APP_DATA]\Microsoft' 9. '[APP_DATA]\Microsoft' 9. '[APP_DATA]\Symantec' 11. '[APP_DATA]\Symantec' 11. '[APP_DATA]\Avg8' 13. '[APP_DATA]\Avg8' 13. '[APP_DATA]\McAfee' 14. '[APP_DATA]\McAfee' 14. '[APP_DATA]\McAfee.com' 15. '[APP_DATA]\Sophos' 16. '*\ntuser.dat' 17. '*\Application Data\Mozilla*' 18. '*\Local Settings\Application Data\Microsoft*' 19. '**,1\tocal Settings\Application Data\Microsoft*' 19. '**,2\tocal Settings\Application Data\Microsoft*' 20. '~\$*.(doc dot ppt x s DOC DOT PPT XLS)' 21. '*\Local Settings\(Temp Tempor~1 History)*' where [APP_DATA] = "C:\Documents and Settings\All Users\Application Data\" (XP) or "C:\ProgramData" (Vista) If you are interested in contributing to the maintenance of this by adding
Backup Source	your suggestions, please <u>contact us</u> . This option is only available when [Custom] CDP type is selected. When
Duckup Source	this option is used, CDP will only backup the files under the paths defined and all other files are ignored.
Backup Filter	This defines whether any file will be backed up by CDP. When CDP type is [Backup all files], it is only possible to exclude files from CDP backup. CDP backup filter is similar to backup set filter, please refer to Backup Filter section for more information.

5.5 Encryption

Before your files are sent to Blaze Vault Server, all your files are compressed and encrypted using your choice of encryption algorithm, mode and key.



The following table explains all encryption parameters available within a backup set.

Note:

Encryption settings are set at backup set creation time and cannot be modified. You need to create a new backup set if you want to change your encryption settings for a backup set.

Parameter	Description
Encryption Algorithm	It defines the encrypting algorithm used to encrypt your backup files. There are three encryption algorithms available:
	[AES] Advanced Encryption Standard algorithm [DESede] Triple DES algorithm [Twofish] Twofish algorithm
	We recommend the use of AES as it has been chosen as the encryption standard for commercial use. Please refer to references on Cryptography for more information about encryption algorithms.
Encryption Mode	It defines the encrypting mode used to encrypt your backup files. There are two encryption modes available:
	[ECB] Electronic Cook Book Mode [CBC] Cipher Block Chaining Mode
	We recommend the use of CBC mode as it offers better security. Please refer to references on Cryptography for more information about encryption modes.
Encrypting Key	The key used to encrypt all files within a backup set. Please write it down on paper and keep it in a safe place. If the key is lost, you will not be able to recover your files from the encrypted backup files.

If you are not familiar with cryptography, it is recommended to use [Default] encryption. By selecting [Default], the encryption key will be your login password.


You can change the encryption key anytime after creating the backup set, by clicking the [Encryption] node of the left panel on the [Backup Setting] dialog. The algorithm and mode cannot be changed however.

5.6 Mapped Network Drive

If you need to backup a mapped network drive on Windows (it will only work in Windows NT/2000/XP/2003/Vista), you must enter your Window's domain, username and password into the [Network Resources Authentication for Windows] section as shown below. It is required because scheduled backups will always run under the context of Window's "Local System" account (which does not have the privileges required to access network resources) by default. Blaze Vault needs to collect your Windows username, password and domain name to authenticate itself to the windows domain controller to acquire the required access privileges to the network files to be backed up. If you don't supply a username and password, Blaze Vault will have problems accessing network resources in its scheduled backup Jobs.

If you need to backup network mapped drive in scheduled backup, please do this:

i. Select the backup set from the drop down list at the top of the left panel




- ii. Enter your Windows domain, username and password into the right panel and press [OK]
- iii. Press the [OK] button to save.

The steps above apply only to computers running in a Windows domain. If you don't have a windows domain with your network and you are using a workgroup or using a NetWare server, please use the "net use" command to authenticate the running backup process against the computer hosting the mapped drive. Otherwise, you will get "Access Denied" error from the backup report.

For example, if you want to backup \\SERVER\SHARE that is located on a NetWare server (or another computer in a windows workgroup) and you are getting "Network drive is not accessible" error message, please try adding the following command as a [Pre-backup command]

net use \\SERVER\SHARE [PASSWORD] /USER:[DOMAIN | MACHINE_NAME]\[USERNAME]

E.g.



Enter one of the following commands directly into the Pre-Backup Command:



net use \\Netware\Data password /USER:peter
net use \\WorkgroupComputer1\Data password /USER:WorkgroupComputer1\peter

This will authenticate the current process with the NetWare server (or another computer in a windows workgroup) and backup will then run correctly.


5.7 Backup Filter

A "Backup Filter" defines the file selection rules that allow user to easily include/exclude files into/from the backup set by applying user defined criteria(s) to the file names or directory names.

There are some basic rules regarding backup filters:

- Filters are checked in creation order. Once inclusion/exclusion has been identified, the remaining filters won't be checked.
- ii. Inclusion/Exclusion made by filter always takes precedence over backup source selections
- iii. If all filters do not apply to a particular file, this file is then checked for inclusion/exclusion backup source selections

To add a new filter, press the [Add] button at the bottom of the right panel.



Key	Description		
Name	The name of a filter		
Top Directory	The top directory to which this filter is applied. Filtering rules will be applied to all files and/or directories under this directory.		
Apply To	Define whether to apply the filtering rule to files and/or directories		
Pattern Matching	It defines the filtering rules of a filter. A filtering rule can be of one of t following types:		
	[Starts With] Include/Exclude all files/directories with name starting with a certain pattern. For example: You can use B* to match all files with		



		name starting with a `B' character	
	[Contains]	Include/Exclude all files/directories with name containing a certain pattern. For example: You can use *B* to match all files with name containing with a 'B' character	
	[Ends With]	Include/Exclude all files/directories with name ending with a certain pattern. For example: You can use *.doc to match all files with name ending with `.doc' (all Word documents)	
	[Regular Expression	Include/Exclude all files/directories with name matching a regular expression.	
	To add a new pattern, press the [Add] button in the [Pattern Matching] area.		
Filter Mode	the backup set. Al	u want to include or exclude matched files into/from so, for those unmatched files, you can choose to filter type) or include (if exclude filter type) them o set.	

Example 1:

If you want to backup only Word, Excel and PowerPoint documents in your document directory (e.g. C:\My Documents), you should setup your backup filter as follows.

Top Directory = C:\My Documents

Apply To = File (true) Matching Type = End With

Matching Patterns = *.doc, *.xls, *.ppt

Filter Mode = Include
Exclude all others = True

Example 2:

If you want to backup all files, excluding all *.exe, *.dll and *.tmp, in C:\Applications, you should setup your backup filter as follows.

Top Directory = C:\Applications Apply To = File (true) Matching Type = End With

Matching Patterns = *.exe,*.dll, *.tmp

Filter Mode = Exclude
Include all others = True

Example 3:

If you have made your selection of files (all under C:\) from the backup source setting but you want exclude all images (e.g. *.jpg and *.gif) from your selection, you should setup your backup filter as follows.

Top Directory = C:\
Apply To = File (true)
Matching Type = End With
Matching Patterns = *.jpg, *.gif
Filter Mode = Exclude
Include all others = false

Please note that the [Include all others] setting is not enabled because you don't want to include all other files (NOT *.jpg, *.gif) under C:\ into the backup set.

Example 4: (advanced)



If you want to include everything, except the "log" directory, under C:\Applications into a backup set, you should setup your backup filter as follows.

Top Directory = C:\Applications Apply To = Directory (true) Matching Type = Regular Expression

Matching Patterns = ^log\$
Filter Mode = Exclude
Include all others = True

Example 5: (advanced)

If you want to include all directories named "log" from the backup set files with file name starting with "B" and ending with "*.doc" under C:\My Documents into the backup set, you can use a regular expression of "^B.*\.doc\$" to do your selection. The filter backup can then be setup as follows.

Top Directory = C:\My Documents

Apply To = File (true)


Matching Type = Regular Expression

Matching Patterns = ^B.*\.doc\$ Filter Mode = Include Exclude all others = True



5.8 Pre/Post-Backup Command

The [Command Line Tool] feature has two major components, the [Pre-Backup] command and the [Post-Backup] command. You can use the [Pre-Backup] or [Post-Backup] commands to run any native OS (operating system) commands before or after running a backup job.



Both [Pre-Backup] and [Post-Backup] commands comprise of the following parameters:

Key	Description		
Name	Name of this Command		
Command	The command to be run (e.g. C:\My Documents\Application.exe or C:\My Documents\BatchJob.bat)		
Working Directory	The directory at which this command will run		

The backup set type affects the time at which [Pre-Backup] and [Post-Backup] commands run. The following table outlines when [Pre-Backup] and [Post-Backup] commands will run in different types of backup set.

Backup Set Type	When Pre-Backup Commands run?	When Post-Commands run?
File	Before uploading backup files	After uploading all backup files
	temporary directory	After spooling backup files to temporary directory (i.e. before the first backup file is uploaded)

Note: You should never backup an application while it is running as this can result in inconsistent and unusable files getting backed up. Please use the "Volume Shadow Copy" feature if you're running Windows XP/2003/Vista or make use of the Pre-Backup Command feature to shutdown your application before running a backup job and use the Post-Backup Command feature to restart your application after the backup job has completed.

For Example

You want to stop Microsoft Outlook using the Pre-Backup Command and restart it after backup using the



Post-Backup Command, create the two following text files and assigned the files to Pre-Backup and Post-Backup Command.

1. Create a text file named "OutlookClose.vbs" using notepad with the following two lines:

```
Set objOLK = createObject("Outlook.Application")
objOLK.quit
```

2. Create a text file named "OutlookStart.bat" using notepad with the following line:

"C:\Program Files\Microsoft Office\OFFICE11\OUTLOOK.EXE"

5.9 Temporary directory

If you are running a file backup job with in-file delta enabled or a database type backup job, Blaze Vault will generate temporary files and the directory that will be used to store all these files are defined by [Options] -> [Temporary directory for storing backup files]. Please set this to a non-system disk partition that has enough free space to avoid problems.

You can set the [Temporary directory for storing backup files] to a mapped network drive. If you choose to do this, please use a UNC path (e.g. \SERVER\SHARE) and don't forget to configure the [Backup Set] -> [Network Resources Authentication for Windows] setting.


5.10 Transfer Block Size

Transfer block size defines the block size Blaze Vault will use to transfer your backup blocks. Generally, backup jobs using a larger block size will have better performance, because of the smaller number of connections involved.

However, some firewalls or proxy servers may block out-going network traffic (HTTP/HTTPS POST method) with large block size for security reasons. If you are in a network with this type of restriction, please lower the transfer size value and try again.

To change the transfer block size of any backup set, please select the [Options] node on the left panel and then you can make changes to the [Transfer Block Size] under [Advanced Options]. After you have made your changes, just press the [OK] button to save.







5.11 Follow Symbolic Link (Linux/Unix/Mac only)

Under Unix/Linux/Mac, users can create a symbolic link to link a file/directory from another directory. This setting defines whether you want Blaze Vault to traverse any symbolic links encountered on your backup path.

To change the follow symbolic link of any backup set, please select the [Options] node on the left panel. You can then make changes to the [Follow Symbolic Link] by checking or un-checking the box. After you have made your changes, just press the [OK] button to save.

5.12 Microsoft's Volume Shadow Copy Service (VSS)

Microsoft Volume Shadow Copy Service (VSS) allows you to backup files that are exclusively opened. Without VSS, you will get the error message "The process cannot access the file because another process has locked a portion of the file" if you are trying to backup a file that is exclusively opened (e.g. Outlook PST file).

Please note that VSS is only available on Windows XP / 2003 / Vista / 2008 and you must have administrative privileges to start the VSS service on a computer. Also VSS will only work if at least one of your partitions is formatted using NTFS.

If you are running Windows 2003, please install the Windows 2003 VSS hot fix available in http://support.microsoft.com/default.aspx?scid=kb;en-us;887827 before running VSS.

If you are running into problems with VSS running on Windows XP / 2003, Microsoft's recommendation is to try re-registering the Volume Shadow Copy Service again. Simply run the script [OBM Home]\bin\RegisterVSS.bat to do so.

For more information, please take a look at the following page for a technical introduction to Volume Shadow Copy Services (VSS):

http://technet2.microsoft.com/windowsserver/en/library/2b0d2457-b7d8-42c3-b6c9-59c145b7765f1033.mspx

5.13 Retention Policy


During backup, if Blaze Vault finds that you have deleted a file (or updated a file) on your computer, it will put the corresponding deleted (or updated) file already backed up on the backup server into a retention area. The retention policy setting defines how long files inside the retention area will be kept on the backup server before they are deleted automatically from the server.

Retention policy will only affect "retained" file (i.e. files that have already been deleted or updated on your computer and thus are moved to the retention area of the backup server). For those files that have not been updated on your computer, the backup of these files is kept in the data area on the backup server and won't be affected by the setting of retention policy. These backup files of unchanged files will stay on the backup server forever until the original files are removed (or updated) from your computer.




Standard Retention Policy

The standard retention policy allows you to delete retained files automatically after a user defined number of days or after a user defined number of backup Jobs. To change the retention policy setting of any backup set, please select the [Retention Policy] node on the left panel. You can then make changes to your retention policy under the [Retention Policy] section. After you have made your changes, just press the [OK] button to save.



Advanced Retention Policy





The [Advanced] retention policy allows you to configure a more flexible retention policy. It allows you to keep a set of snapshots of all backup files based on the time of the backup Jobs. For example, you can configure the advanced retention policy to keep the following sets of backup files to mimic the retention policy of the old days when you were still doing tape rotations:

- ◆ All files available within the last 7 days
- ♦ All files available on the last 4 Saturdays within the last 28 days
- ♦ All files available on the 1st day of each month within the last 3 months
- ♦ All files available on the 1st day of each quarter within the last 12 months
- ♦ All files available on the 1st day of each year within the last 7 years

To do so, you need to setup your advanced retention policy as follows:

- ◆ Type = Daily; Number of copy to keep = 7
- ◆ Type = Weekly; Frequency = Saturday; Number of copy to keep = 4
- ◆ Type = Monthly; Frequency = Day 1; Number of copy to keep = 3
- ◆ Type = Quarterly; Frequency = Day 1 of Jan, Apr, Jul, Oct; Number of copy to keep = 4
- ◆ Type = Yearly; Frequency = Date 01-01; Number of copy to keep = 7

Assuming today is 17-Jan-2006, if [Remove retention files for overlap policy] is NOT enabled, a total of 22 snapshots (provided you have run backups daily for more than 7 years) will be kept on the server accordingly, i.e.:

Daily	Weekly	Monthly	Quarterly	Yearly
16-Jan-2006	14-Jan-2006	01-Jan-2006	01-Jan-2006	01-Jan-2006
15-Jan-2006	07-Jan-2006	01-Dec-2005	01-Oct-2005	01-Jan-2005
14-Jan-2006	31-Dec-2005	01-Nov-2005	01-Jul-2005	01-Jan-2004
13-Jan-2006	24-Dec-2005		01-Apr-2005	01-Jan-2003
12-Jan-2006				01-Jan-2002
11-Jan-2006				01-Jan-2001
10-Jan-2006				01-Jan-2000

If [Remove retention files for overlap policy] is enabled, only the following snapshots are kept:

Daily	Weekly	Monthly	Quarterly	Yearly
16-Jan-2006	14-Jan-2006	01 Jan 2006	01 Jan 2006	01-Jan-2006
15-Jan-2006	07-Jan-2006	01 Dec 2005	01 Oct 2005	01-Jan-2005
14 Jan 2006	31 Dec 2005	01 Nov 2005	01 Jul 2005	01-Jan-2004
13 Jan 2006	24 Dec 2005		01 Apr 2005	01-Jan-2003
12 Jan 2006				01-Jan-2002
11 Jan 2006				01-Jan-2001
10 Jan 2006				01-Jan-2000




The weekly policy overrides the daily policy so the snapshots of 10-Jan-2006, 11-Jan-2006, 12-Jan-2006, 13-Jan-2006 and 14-Jan-2006 are removed. The monthly policy overrides the weekly policy so the snapshots of 24-Dec-2005 and 31-Dec-2005 are removed. The same applies to the monthly, quarterly and yearly policy giving a total of 11 snapshots.

5.14 Extra Backup (Off-Line backup, Logout Reminder)

Off-line backup is basically designed for notebook users who are off-line most of the time and cannot rely on the backup schedule to backup regularly. The "Backup Interval" allows notebook users to specify the interval that they would like their data to backup. When the machine is online and this interval has elapsed, backup will run automatically. If [Off-Line Backup Alert] is enabled, a popup message box will ask the user to confirm starting the backup.

The [Email Notification] setting is the number of days since the last backup that triggers the backup server to send email notification to the client to remind him to run an off-line backup.

When the [System Logout Backup Reminder] setting is enabled, a popup message box will ask the user to start a backup before logging out / shutting down Windows.



5.15 In-File Delta


Please refer to the in-file delta section for more information on this topic.


5.16 Local Copy

If you want to save an extra copy of backup data on your local hard disk (in addition to a copy of backup data stored on the backup server) to minimize file-restoring time and/or to provide an extra safety precaution, you can do the following:




- i. Open Blaze Vault from the System Tray (see previous sections for details)
- ii. Setup your backup set (see previous sections for details)





- iv. Check the [Copy to Local Hard Disk] checkbox
- v. Enter a directory to where you want an extra copy of your backup files to be stored in the [Copy to] field provided (preferably a directory under another hard disk)
- vi. An extra copy of backup will be saved in the [Copy to] directory when you run your backup job





If you want to make local copy to a directory located on a NetWare server (or another computer is a windows workgroup) and you are getting "Network drive is not accessible" error message, please try adding the following command as a [Pre-backup command]

net use \\SERVER\SHARE [PASSWORD] /USER:[DOMAIN | MACHINE_NAME]\[USERNAME]

E.g.


C:\> net use \\Netware\Data password /USER:peter
C:\> net use \\WorkgroupComputer1\Data password /USER:WorkgroupComputer1\peter

This will authenticate the current process with the NetWare server (or another computer is a windows workgroup). Backup will then be allowed to run correctly.


How to restore "Local Copy" files

"Local Copy" files are stored in the [Copy to] directory (under [Local Copy] setting). To restore backup files, please do the followings:

- i. Press the button on the main page of Blaze Vault dialog.
- ii. Select the required [Backup Set] from the list and press [Next] to proceed.
- iii. Fill in the [Source Directory] (directory where "Local Copy" files are stored) and [Destination Directory] (directory to where you want "Local Copy" files to be restored)




iv. Click [Start Decrypt], and when it finishes you can see something similar to the following on the screen:





5.17 Using One Backup Account for Multiple Computers

Blaze Vault allows you to backup multiple computers using a single backup account. To backup multiple computers, you need to create a different backup set to backup each individual computer and to configure the [Run scheduled backup on this computer] checkbox, which is placed under the [Backup Schedule] node.



For version 5.2 or above

Since the computer that created the backup set will have its computer name associated with the backup set. The backup scheduler running on each computer will only run backup sets with the same computer name as itself. Thus, you just need to make sure that all your computer names using a single backup account are unique.

For version 5.1 or Earlier

You must configure Blaze Vault on each computer that it only runs scheduled backup for the intended backup sets only. If this is not setup properly, scheduled backup job of the same backup set from different computers will both be started. This will result in lots of checksum errors and files being deleted on the backup server.

To allow multiple computers to be backed up under a single backup account, you are required to do the following **for each computer** that has installed Blaze Vault under the same backup account:

- i. Logon to one of the computers that has Blaze Vault installed under the same backup account.
- ii. Open Blaze Vault and select a backup set that is not intended to run on this computer from the left panel.
- iii. Make sure that the [Run scheduled backup on this computer] checkbox on the right panel is not checked.
- iv. Repeat the previous step for the rest of the backup sets that are not intended to run on this computer.
- v. Repeat steps ii to iv for each computer that has Blaze Vault installed under the same backup account.



IMPORTANT If you create a new backup set or want to backup another computer using the same backup account at a later date (this implies that you need to create an additional backup set under this backup account for the new computer), please make sure to repeat the procedure above (i.e. uncheck the [Run scheduled backup on this computer] checkbox for the added backup set) for each computer.




6 Backing Up Files

This chapter describes how files are backed up by Blaze Vault to the backup server

6.1 How files are backed up

The diagram below describes how Blaze Vault backup your files.



Run backup at scheduled time automatically

Once you set your backup scheduled, a backup job will be started automatically to perform backup operation for you at your absence. You can have backup running at your scheduled time as often as you want (e.g. twice a day or hourly during office hour) without requiring doing any extra work.

Incremental Backup

Unchanged files are already backed up to server and need not to be backed up again. Blaze Vault will pick the new or updated files from your backup set files and upload only these files to the server. It significantly reduces the time required to perform the backup operation since most users update less than 5% of their total data each day.

Compress and encrypt data automatically

Data are compressed and encrypted before they are uploaded to the server. Not only does it reduce the storage space to keep you backup files, it also ensures the privacy of your data.

File Retention Policy

The built-in file retention policy allows you to access multiple versions of the same file or even deleted files from your backup set. Backup files are put into a retention area before they are removed from the server. If you want to get back a deleted file (or you want to get back the previous versions of an updated files)

within the retention period, these files will always be available in the retention area. This feature is particularly useful when you have accidentally deleted a file or incorrectly updated a file within the file retention period (file retention period is user customizable).

6.2 Backup files directly to the backup server

You can backup your data to Blaze Vault Server by following instructions below.

- i. Open Blaze Vault.
- ii. Right click Blaze Vault icon available in the system tray and choose [Open].
 - a. To start setting up backup sets, click the button to open the [Backup Setting] dialog.
 - b. On the left panel, press the 🖹 button to create a new backup set.
 - c. Enter a name for your backup set.




d. Select the files/directories you want to backup.






Press [Advance] to add more files to the backup set.



e. Set the backup schedule (Note: You can have more than one schedule in a backup set).



f. Set the encryption algorithm, encryption mode and encrypting key for this backup set (Hint: For the sake of simplicity, just select the [Default] radio button (your encrypting key is set to be the same as your backup account password).





iii. Run Backup

- a. Press the [Backup] button on the main page of Blaze Vault dialog.
- b. Select the backup set you want to run and select [Offsite Backup Server] to start backing up your files to Blaze Vault Server. If applicable, you can change the In-File Delta Type also.



c. Press [OK] to start the backup job.

Note:

- 1. You can have more than one backup set in a backup account.
- Please w rite the encrypting key down on paper and keep it in a safe place. If you lose your encrypting key, you will not be able to restore your backup files.


6.3 Backup files to removable hard disk (seed loading)

If you have a lot of data (e.g. 300GB) to backup to the backup server, it would take a considerable amount of time to perform the first full backup through the Internet. If you run into this problem, you can use the Seed Loading Utility to backup your backup set to local hard disk (instead of directly to the backup server) and then transport the backup data, using removable hard disk, to Blaze Vault Server. The administrator can then load all your backup files from your removable hard disk into your backup account. This could then save you days (even weeks) of performing your first full backup. Since subsequent backup will be incremental backup (only new or updated files will be uploaded to the server) you should have no problems uploading your backup data afterwards.

To perform seeding loading, please do the following:




- i. Open Blaze Vault from the System Tray (see previous sections for details).
- ii. Setup your backup set (see previous sections for details).
- iii. Select the backup set you want to run and select [Local Hard Disk (Seed Load Utility)] to start backing up your files to local hard disk. In the field under the option, enter a directory where you want all backup files to be stored.



iv. Please make sure you have enough free space in the directory specified. If you are going to transport a removable hard disk to Blaze Vault Server, please enter a directory under your removable hard disk here.

Press the [OK] button to start the backup job.

v. You should get the message "Backup Completed Successfully" as shown below after all backup files are spooled to the directory you specified.



vi. Transport the data in the specified directory to Blaze Vault Server.



7 Restoring Files

This chapter describes different ways files can be restored from the backup server

It is very important to write down your encrypting key on paper and keep it in a safe place because there will be no way to restore your backup files if you lose your encrypting key.

7.1 Restore backup files directly from backup server

You can use either Blaze Vault or the web restorer to restore backup files from the backup server.

Using Blaze Vault


You can restore your data from the backup server by following instructions below.

- i. Open Blaze Vault from the System Tray (see previous sections for details).
- ii. Select the [Restore] button on the left of the main page of Blaze Vault dialog.
- iii. Select the backup set from which you would like files to be restored from the list.






iv. Select the snapshot of your backup files that you would like to restore from the backup server by using [Show files after Job] drop down list



- Use the [Change] button to select the directory to where you want files to be restored (or simply select [Original location] to restore files to their original path).
- vi. Select the files that you would like to restore and press the [Start Restore] button to start.
- vii. Files will be restored automatically as shown below (a file won't be downloaded from the backup server again if an identical file exists on local path already).





Using the web interface

You can restore your data from Blaze Vault Server by following instructions below.

- i. Logon to the Blaze Vault Server web interface
- ii. From the top menu, click [File Explorer]



iii. Select the [Backup Set] that contains the files that you want to restore by clicking on the links



iv. Select the snapshot of your backup files that you would like to restore from the backup server by using [Show files As Of] drop down list



v. If you want to see all the different versions of all files (shown as gray below), just choose the [Show all files] radio button on the [File Explorer] page.

Files, which are shown in gray below (e.g. Copy of test.txt), are being stored in the retention area on the backup server but you can still restore these files from the backup server.




- vi. Select the files that you would like to restore and press the [Restore] button on the toolbar
- vii. A dialog shown below would appear





Troubleshooting:

- Make sure you have clicked the 'Yes' button on the security warning dialog box. If you have clicked the 'No' button already, please restart your browser and try again.
- a. Press the [Restore] button
- Enter the directory to which backup files should be restored to in the [Restore files to] textbox
- c. Enter the encrypting key which will be used to decrypt your backup files upon restoring your backup files
- d. Press the [Start] button to start restoring







7.2 Restore backup files from removable hard disk

If you want to restore lots of backup files from the backup server and you find it too slow to restore all your backup files from the backup server through the internet. You can ask your backup services provider to send you all your backup files in removable hard disk (or CD/DVD). However, all backup files stored on backup server are in encrypted format. You need to decrypt them back to their original format before you can use them. To decrypt your backup files from removable media, please do the followings:

- i. Open Blaze Vault from the System Tray
- ii. Press the | button to start the [Decrypt Files Wizard].
- iii. Use the [Change] button to locate the "files" directory (provided by your backup provider in removable hard disk or DVD) which contains the backup files that you want to decrypt




iv. If you have more than one backup set under the "files" directory, select the [Backup Set] which contains the backup files that you want to decrypt




v. Select the snapshot of your backup files that you would like to restore from the removable media by using [Show files after Job] drop down list





- vi. If you want to see all the different versions of all files (shown as gray below), just choose the [Show all files] radio button on the [Decrypt Files Wizard] dialog.
- vii. Use the [Change] button to select the directory to where you want files to be restored (or simply select [Original location] to restore files to their original path).
- viii. Press the [Start Decrypt] button to start restoring. When it finishes, you will see a screen similar to the following:



7.3 IP addresses Restriction for Online Restore

Online file restore operation can be restricted by IP addresses. You can ask your backup service provider to restrict online file restoration for your backup sets by IP addresses to only allow people from authorized IP addresses to restore files from the backup server. To check if online file restore of any backup set is restricted this way, please logon to the web interface of Blaze Vault Server, and check the section of [Backup Set] -> [Online Restore IP restriction] (shown below).



Users are not allowed to update the [Online Restore IP restriction] directly. Please ask your backup services provider to do the changes for you.

[Help] Post-backup command			
1 . Name		[<u>Add</u>]	
Command			
Working Directory			
[Help] Online Restore IP restrict 1. Only from 82.144.244 [Help] Fig. Enable Continuous	.10 to 82.144.244.10		
Time Mark Interval: 60 ▼	Minute		
Minimum Update Interval: Backup these files upon cha			



8 In-File Delta Technology

The chapter describes what in-file delta technology is and how in-file delta can be used to backup large database files (e.g. a 10GB Outlook.pst file) without uploading the whole database file everyday.

8.1 Overview

In-file delta technology is an advanced data block matching algorithm which has the intelligence to pick up changes (delta) of file content between two files. Using this algorithm, daily backing up of large files (e.g. a 10GB Outlook.pst file) over low-speed internet connection is made possible because it requires only the changes of information (should be marginal) since the last backup to be sent over a low-speed internet connection to complete the backup of a large file (here we assume that the full backup of the file has been saved on the backup server already).

This is what will happen in the backup of a 10GB Outlook.pst file when it is backed up by Blaze Vault with in-file delta technology.

- i. The whole files (10GB), along with its checksum file, are backed up to the backup server. This can be done directly through the internet or indirectly using the <u>seed loading utility</u> on a removable hard disk.
- ii. When backup runs again later (normally the next day), Blaze Vault will download a checksum listing of all data blocks of the full backup file (or last incremental backup file) from the backup server and use it to pick up all changes that have been made to the current Outlook.pst file.
- iii. Changes detected are then saved in a delta file which is uploaded to the backup server. A new checksum file is generated and is also uploaded. (This delta file is assumed to be small because the content of PST files doesn't change a lot during daily usage)
- iv. Subsequent backups of this 10GB Outlook.pst file will go through step ii and step iii again. As explained, only a small delta file and checksum file will be uploaded to the backup server.
- v. With in-file delta technology, daily backing up of large file over low-speed internet connection is now possible

Incremental in-file delta type

Incremental Delta will facilitate ease of backup. The delta is generated by comparing with the latest uploaded full or delta file. The delta file generated is the smallest possible and uses the least bandwidth during backup. For restoration, the full file and all delta files up to the required point-in-time is required to restore the file to a specific point-in-time.

Example: If you are adding around 100MB changes to a 10G Outlook.pst everyday.

After the first full backup job, Blaze Vault will continue to generate and upload delta files instead of uploading the full file until either one of the following two rules are true:

- a) Number of deltas generated since the last full backup is greater than the [No. of Delta] setting.
- b) The delta ratio (the ratio of the delta file size against the full file size) is greater than the [Delta Ratio] setting

Using incremental delta, the delta generated by comparing the current file with the latest uploaded full or delta file is around 100MB.

Since the delta file size is around 100MB daily, the delta ratio (around 1%) will not trigger a full file upload. Instead Blaze Vault will continue to generate and upload delta files until day 102 (assuming the full file was uploaded on day 1) when the number of deltas generated exceeds the [No. of Delta] setting and triggers the upload of the full Outlook.pst file. You can disable the [No. of Delta] and [Delta Ratio] if you don't want



to upload the full file.

All delta files are generated with respect to changes made since the last incremental or full backup. This means that the last full backup file and **ALL** incremental delta backup files are required to restore the latest snapshot of a backup file.

Differential in-file delta type

Differential Delta will facilitate ease of restore. The delta is generated by comparing with the latest uploaded full file. The delta file generated grows daily and uses more bandwidth during backup. For restoration, the full file and a single delta file is required to restore the file to a specific point-in-time.

Example: If you are adding around 100MB changes to a 10G Outlook.pst everyday.

After the first full backup job, Blaze Vault will continue to generate and upload delta files instead of uploading the full file until either one of the following two rules are true:

- c) Number of deltas generated since the last full backup is greater than the [No. of Delta] setting.
- The delta ratio (the ratio of the delta file size against the full file size) is greater than the [Delta Ratio] setting


Using differential delta, the delta generated by comparing the current file with the latest uploaded full file is around 100MB for the 1^{st} delta, 200MB for the 2^{nd} delta, 300MB for the 3^{rd} delta and so on.

Since the delta file grows by 100MB daily, the delta ratio for day 52 (delta file size is approximately 51x100 = 5.1GB, assuming the full file was uploaded on day 1) being over 50% exceeds the [Delta Ratio] setting and triggers the upload of the full Outlook.pst file. You can disable the [No. of Delta] and [Delta Ratio] if you don't want to upload the full file.

All delta files are generated with respect to changes made since the last full backup file (i.e. differential backup). This means that only last full backup file and the last delta file are required to restore the latest snapshot of a backup file. This means that other intermediate delta files are only required if you want to restore other snapshots of a backup file.

Differential in-file delta backup has the benefits that a corrupted delta file would only make one particular version of a backup file non-recoverable and all other backups created by other delta files of the same file would still be intact.







8.2 Block Size

The block size defines the size of data block being used to detect the changes between the last full or delta backup file and the file sitting on the local computer right now. In general, the smaller the block size, the more likely a matched data block can be found between the last backup file and the file on local computer. It, therefore, produces a smaller delta file but it would require more processing power to detect these changes. On the other hand, in-file delta backup running with larger block size will run faster but this will generally produce a larger delta file.

In most case, the default setting [Auto] will choose the optimal block size for each file (depending on the size of the file) for you.

8.3 Minimum File Size

The [Minimum Size] setting defines the smallest file size a file must have before the use and application of in-file delta backup technology.

If the size of a file that is being backed up is smaller than the [Minimum Size] setting, in-file delta backup technology won't be applied to this file and the whole file, instead of just the delta file, will be uploaded to the backup server. It is not necessary to perform in-file delta backup on small files because backing up the whole file doesn't take too long anyway. Backing up the whole file instead reduces the time required to restore a backup file.

8.4 Uploading full file again

No. of Delta

The [No. of delta] setting defines the maximum number of delta files from the same full backup file to be generated and backed up to the backup server before a full backup (the whole file) of this file is uploaded to the backup server instead.

For example, if you have created 100 delta files from the full backup file already and the [No. of delta] setting is set to 100, the next backup will upload a full backup file (the whole file) instead of just the delta file. However, if the [No. of delta] rule is disabled, it will keep generating delta files and uploading these delta files to the backup server until the other delta rule forces a full backup (i.e. delta ratio exceeded). This setting is here to make sure that there will always be a full backup file after a certain number of delta files have been generated.

Delta Ratio

The [Delta Ratio] setting is defined to be the size of a delta file divided by the size of its full back up files (i.e. the percentage of changes detected between the last full backup file and the current file).


If the delta ratio calculated from the size of the generated delta file and the size of the full backup file is greater than the [Delta Ratio] setting, the whole file, instead of just the delta file, will be backed up to the backup server. It is done this way because the difference between backing up the whole file and the delta file is not significant and it is better to upload the whole file instead to reduce the time required to restore the file.

The default setting of [Delta Ratio] is 50%. This means that if a file changes by more than 50%, the whole file, instead of just the delta file, will be backed up and uploaded to the backup server.



8.5 Advanced In-file delta type

The [In-file delta] -> [Advanced] setting allows users to override default in-file delta type when on a certain number of days (e.g. all Sundays or the $\mathbf{1}^{st}$ day of each month). This is useful if you want all in-file delta backups to be incremental but you want to do a differential in-file delta backup on Saturdays as well as the full file backups on the $\mathbf{1}^{st}$ day of every month. If you want to do this, simply press the [Advanced] button and the [Advanced In-File Delta Type Setting] dialog will be popped up as shown below.



With this setting, all backup Jobs on Saturdays will be differential in-file delta backups, backups for the 1st day of each month will run a full backup. This ensures that all backup files will be backed up in full at a regular interval. One benefit of this is that restore time will run faster because of less delta merging. Another benefit is that the risk of a corrupted incremental delta file resulting in data loss is much lower because a full backup is always available periodically.



9 Backup/Restore Oracle 8i / 9i / 10g / 11g

This chapter will describe in details how Blaze Vault backup your Oracle Database Server and how you can restore an Oracle database using the backup files.

9.1 Requirements

- i. Blaze Vault must be installed onto the computer that can connect to your Oracle Database Server using TCP/IP protocol.
- ii. Data from Oracle database will be backed up to a temporary directory before they are sent to Blaze Vault Server. Please make sure you have sufficient space on your computer to store these data when you run the backup job.
- iii. Database must be in archived log mode

To switch database to archived log mode, please do the following:

a. Set the parameters below in the PFILE to enable automatic archiving

```
\label{log_archive_def} $\begin{subarray}{l} LOG\_ARCHIVE\_DEST = [\emph{directory where archive redo logs will be stored}] \\ LOG\_ARCHIVE\_FORMAT = 'log%t\_%s\_%r.arc' \\ LOG\_ARCHIVE\_START = TRUE \\ \end{subarray}
```

b. Set ORACLE_SID to your database's System Identifier (SID)

```
export ORACLE_SID=GDB1 (assuming your database's SID is GDB1)
```

c. Run SQL Plus and connect to database as SYSDBA

```
For Oracle 9i/10g/11g
```

```
sqlplus "/ as sysdba"

For Oracle 8i

connect internal;
```

d. Shutdown database

shutdown immediate

e. Start and mount database

startup mount

f. Switch database to archived log mode

```
alter database archivelog;
```

g. Open database

alter database open;

```
Oracle 10g Example:

$ export ORACLE_SID=GDB1

$ sqlplus "/ as sysdba"

$QL*Plus: Release 10.2.0.1.0 - Production on Thu Nov 8 15:08:57 2007

Copyright (c) 1982, 2005, Oracle. All rights reserved.

Connected to:
```



```
Oracle Database 10g Enterprise Edition Release 10.2.0.1.0 - Production
With the Partitioning, OLAP and Data Mining options

SQL> shutdown immediate
Database closed.
Database dismounted.
ORACLE instance shut down.

SQL> startup mount
ORACLE instance started.

Total System Global Area 285212672 bytes
Fixed Size 1218992 bytes
Variable Size 96470608 bytes
Database Buffers 184549376 bytes
Redo Buffers 2973696 bytes
Database mounted.

SQL> alter database archivelog;
Database altered.

SQL> alter database open;
Database altered.
```

iv. JAVASYSPRIV role is granted to system account

You can grant this role to system account by executing:

h. Grant permission to system account

For Oracle 9i/10q/11q

```
SQL> grant javasyspriv to system;
For Oracle 8i
SVRMGRL> connect internal
SVRMGRL> @?/javavm/install/initjvm.sql;
SVRMGRL> @?/rdbms/admin/catalog.sql;
SVRMGRL> @?/rdbms/admin/catproc.sql;
SVRMGRL> @?/javavm/install/initdbj.sql;
SQL> grant javasyspriv to system;
```

Oracle 9i/10g/11g Example: SQL> grant javasyspriv to system; Grant succeeded.

9.2 Overview

Blaze Vault will backup your Oracle database by taking the following steps.

- i. Connect to the Oracle database using SQL*NET over TCP/IP
- ii. Run all Pre-Commands of this backup set
- iii. If the backup type to run is [Database Backup type],
 - all data files in each of the tablespace(s) selected are copied to the temporary directory specified by this backup set
 - b. if there are temporary files in the database, the script to re-create the temporary files



are generated to a file located in the temporary directory specified by this backup set

- all non-default initialization parameters will be spooled to an initializing file located in the temporary directory specified by this backup set
- d. all control files will be copied to the temporary directory specified by this backup set
- all archived log files will be copied to the temporary directory specified by this backup set
- iv. If the backup type to run is [Archived Log Backup type],
 - all archived log files will be copied to the temporary directory specified by this backup set
- v. Run all Post-Commands of this backup set
- vi. Upload all files copied to the temporary directory to Blaze Vault Server
- vii. Remove temporary files from the temporary directory

Note:

If your Oracle database is running on Windows, please install Blaze Vault onto the company running the Oracle database if Blaze Vault is to backup this Oracle database. This would shorten the time required to backup the Oracle database.

9.3 How to backup an Oracle Database (Physical Backup)

Please follow the instructions below to backup your Oracle database to Blaze Vault Server.

- i. Install Blaze Vault onto your computer.
- ii. Open Blaze Vault.

Right click Blaze Vault icon available in the system tray and choose [Open].




- iii. Create a backup set.
 - a. To start setting up backup sets, click the button to open the [Backup Setting] dialog.
 - b. On the left panel, press the 🔳 button to create a new backup set.
 - c. On the dialog, choose [Oracle Database Server Backup] as the [Type].






d. Enter a name for your backup set.




- e. Enter the system password, the Oracle Database Server Host Name, TNS Port and SID.
- f. Select the tablespace(s) you want to backup.




g. Set the backup schedule for database backup and archived log backup.





Note: You can have more than one schedule in a backup set, i.e. you can perform intraday transaction log backup by adding more than one daily transaction log backup schedule to your backup set.


h. Set the encryption algorithm, encryption mode and encrypting key for this backup set.



Hint: For maximum security, please select AES (Advanced Encryption Standard) Algorithm, CBC (Cipher Block Chaining) mode and use an encrypting key with more than 8 characters.


- iv. Run Backup.
 - a. Press the [Backup] button on the main page of Blaze Vault dialog.
 - b. Select the backup type (e.g. Database Backup, Archived Log Backup) you would like to perform. Select the backup set you want to run and select [Offsite Backup Server] to start backing up your files to Blaze Vault Server. If applicable, you can change the In-File Delta Type also.





c. Click [OK] to start backing up your files to Blaze Vault Server.





9.4 How to restore an Oracle Database

Please follow the instructions below to restore your Oracle 9i/10g/11g databases from Blaze Vault Server.



i. Download the backup files from Blaze Vault Server.

Please refer to the [Quick Start - Backup File] section for information on how to download backup files from Blaze Vault Server.

ii. For restore an existing database

Shutdown the database

To shutdown the database, please do the following:

- a. Set ORACLE_SID to your database's System Identifier (SID)
 - \$ export ORACLE SID=GDB1 (assuming your database's SID is GDB1)
- b. Run SQL Plus and connect to database as SYSDBA
 - \$ sqlplus "/ as sysdba"
- c. Shutdown database

SQL> shutdown immediate

```
Oracle 9i/10g/11g Example:

$ export ORACLE_SID=GDB1

$ sqlplus "/ as sysdba"

SQL*Plus: Release 10.2.0.1.0 - Production on Thu Nov 8 17:04:57 2007

Copyright (c) 1982, 2005, Oracle. All rights reserved.

Connected to:
Oracle Database 10g Enterprise Edition Release 10.2.0.1.0 - Production With the Partitioning, OLAP and Data Mining options

SQL> shutdown immediate
Database closed.
Database dismounted.
ORACLE instance shut down.
```

For recover a database that currently does not exist

Create a password file

 $\$ orapwd file= $\$ORACLE_HOME/dbs/orapwGDB1$ password=pwd123 (assuming your database's SID is GDB1, and password is pwd123)

```
Oracle 9i/10g/11g Example:

orapwd file=/oracle/OraHome1/dbs/orapwGDB1 password=pwd123
```

iii. Put all downloaded backup files in place

Control files, data files and archived logs are stored on Blaze Vault Server along with their full path information. You just need to put all these files back to their original locations when performing a database restore.

For example:

```
/obm_restore/Oracle Database Server/oracle/product/10.2.0/db_1/admin/GDB1/
/obm_restore/Oracle Database Server/oracle/product/10.2.0/db_1/dbs/initGDB1.ora
/obm_restore/Oracle Database Server/oracle/product/10.2.0/db_1/dbs/spfileGDB1.ora
/obm_restore/Oracle Database Server/oracle/product/10.2.0/db_1/flash_recovery_area/GDB1/
```



/obm restore/Oracle Database Server/oracle/product/10.2.0/db 1/oradata/GDB1/

Move to

```
/oracle/product/10.2.0/db_1/admin/GDB1/
/oracle/product/10.2.0/db_1/dbs/initGDB1.ora
/oracle/product/10.2.0/db_1/dbs/spfileGDB1.ora
/oracle/product/10.2.0/db_1/flash_recovery_area/GDB1/
/oracle/product/10.2.0/db_1/oradata/GDB1/
```

iv. Rename database files (Only for restoring database to a new location)

Rename your database files by doing the following:

a. Modify the PFILE to update file path

Open the PFILE (\$ORACLE_HOME/dbs/initGDB1.ora), change every file path to the new location, and then save it

For example:

b. You may need to quote the values of dispatchers as a single argument.

Add double quotation marks

```
dispatchers = "(PROTOCOL=TCP) (SERVICE=GDB1XDB)"
```

c. Delete the SPFILE

Delete the SPFILE (\$ORACLE_HOME/dbs/spfileGDB1.ora)

- d. Set ORACLE_SID to your database's System Identifier (SID)
 - \$ export ORACLE_SID=GDB1 (assuming your database's SID is GDB1)
- e. Run SQL Plus and connect to database as SYSDBA

```
$ sqlplus "/ as sysdba"
```

f. Start and mount database

```
SQL> startup mount
```

g. Create a backup of the control file to trace file

SQL> alter database backup controlfile to trace as '/New_DB_Location/control.trc' reuse; (assuming you create a trace file to /New_DB_Location/)



h. Rename each of data file, log file and tempfile

Open the trace file that just created, and then check for the filename of each datafile, log file and tempfile.

Please do the following to rename each of the files:

```
SQL> ALTER DATABASE RENAME FILE 'xxx' TO 'yyy'; where xxx is the old filename found in the trace file, and yyy is the new filename with updated path
For example:
SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db_1/oradata/GDB1/system01.dbf' TO
'/new_db_location/oradata/GDB1/system01.dbf';
SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db 1/oradata/GDB1/undotbs01.dbf' TO
'/new db location/oradata/GDB1/undotbs01.dbf';
SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db 1/oradata/GDB1/sysaux01.dbf' TO
 /new_db_location/oradata/GDB1/sysaux01.dbf';
SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db_1/oradata/GDB1/users01.dbf' TO
 /new db location/oradata/GDB1/users01.dbf';
SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db 1/oradata/GDB1/TS1' TO
'/new_db_location/oradata/GDB1/TS1';
 \textbf{SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db\_1/oradata/GDB1/redo01.log' \ \textbf{TO} } \\ 
'/new_db_location/oradata/GDB1/redo01.log';
SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db 1/oradata/GDB1/redo02.log' TO
'/new_db_location/oradata/GDB1/redo02.log';
SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db 1/oradata/GDB1/redo03.log' TO
'/new db location/oradata/GDB1/redo03.log';
SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db_1/oradata/GDB1/temp01.dbf' TO
 /new_db_location/oradata/GDB1/temp01.dbf';
```

```
Oracle 9i/10g Example:
$ export ORACLE SID=GDB1
$ sqlplus "/ as sysdba"
SQL*Plus: Release 10.2.0.1.0 - Production on Fri Nov 9 17:50:30 2007
Copyright (c) 1982, 2005, Oracle. All rights reserved.
Connected to an idle instance.
SQL> startup mount
ORACLE instance started.
Total System Global Area 285212672 bytes
Fixed Size 1218992 bytes
Variable Size 92276304 bytes
Database Buffers 188743680 bytes
Redo Buffers 2973696 bytes
Database mounted.
SQL> alter database backup controlfile to trace as '/new db location/control.trc' reuse;
 SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db_1/oradata/GDB1/system01.dbf'
TO '/new_db_location/oradata/GDB1/system01.dbf';
SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db_1/oradata/GDB1/undotbs01.dbf
TO '/new_db_location/oradata/GDB1/undotbs01.dbf';
Database altered
SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db_1/oradata/GDB1/sysaux01.dbf'
TO '/new_db_location/oradata/GDB1/sysaux01.dbf';
SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db_1/oradata/GDB1/users01.dbf'
TO '/new_db_location/oradata/GDB1/users01.dbf'
```

```
Database altered.

SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db_1/oradata/GDB1/TS1' TO '/new_db_location/oradata/GDB1/TS1';

Database altered.

SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db_1/oradata/GDB1/redo01.log' TO '/new_db_location/oradata/GDB1/redo01.log';

Database altered.

SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db_1/oradata/GDB1/redo02.log' TO '/new_db_location/oradata/GDB1/redo02.log';

Database altered.

SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db_1/oradata/GDB1/redo03.log' TO '/new_db_location/oradata/GDB1/redo03.log';

Database altered.

SQL> ALTER DATABASE RENAME FILE '/oracle/product/10.2.0/db_1/oradata/GDB1/redo03.log' TO '/new_db_location/oradata/GDB1/redo03.log';

Database altered.
```

v. Restore Database

Use Recovery Manager to restore your database by doing the following:

For Oracle 9i/10g/11g

- a. Set ORACLE_SID to your database's System Identifier (SID)
 - \$ export ORACLE_SID=GDB1 (assuming your database's SID is GDB1)
- b. Run Oracle Recovery Manager (rman) and connect to the target database
 - \$ rman target /
- c. Start and mount database

RMAN> startup mount

d. Reapply all transactions from the archived log files to the last sequence

RMAN> recover database until sequence=4 thread=1; (assuming the sequence number of your last archived redo log is 3)

Sequence number are named on the filename of archived redo log

- e.g. /oracle/OraHome1/dbs/o1_mf_1_2_3m5h1svs_.arc
 /oracle/OraHome1/dbs/o1_mf_1_3_3m5h1yby_.arc
 in this case, the sequence number of archived redo log is 4.
- e. Open database

RMAN> alter database open resetlogs;

```
Oracle 9i/10g/11g Example:

$ export ORACLE_SID=GDB1

$ rman target /

Recovery Manager: Release 10.2.0.1.0 - Production on Thu Nov 8 17:46:27 2007

Copyright (c) 1982, 2005, Oracle. All rights reserved.

connected to target database (not started)

RMAN> startup mount
```



```
Oracle instance started
database mounted
Total System Global Area 285212672 bytes
                                   1218992 bytes
113247824 bytes
167772160 bytes
2973696 bytes
Variable Size
Database Buffers
Redo Buffers
  NMAN> recover database until sequence=4 thread=1;
Starting recover at 08-NOV-07
Starting implicit crosscheck backup at 08-NOV-07
using target database control file instead of recovery catalog
allocated channel: ORA DISK 1
channel ORA_DISK_1: sid=157_devtype=DISK
Finished implicit crosscheck backup at 08-NOV-07
Starting implicit crosscheck copy at 08-NOV-07 using channel ORA DISK 1 Finished implicit crosscheck copy at 08-NOV-07
searching for all files in the recovery area cataloging files... cataloging done \,
List of Cataloged Files
-----
File Name:
/oracle/product/10.2.0/db_1/flash_recovery_area/GDB1/archivelog/2007_11_08/o1_mf_1_3_3m5
hlyby_.arc
using channel ORA DISK 1
starting media recovery
archive log thread 1 sequence 2 is already on disk as file /oracle/product/10.2.0/db_1/flash_recovery_area/GDB1/archivelog/2007_11_08/o1_mf_1_2_3m5 hlsvs_.arc archive log thread 1 sequence 3 is already on disk as file /oracle/product/10.2.0/db_1/flash_recovery_area/GDB1/archivelog/2007_11_08/o1_mf_1_3_3m5
archive log filename=/oracle/product/10.2.0/db_1/flash_recovery_area/GDB1/archivelog/2007_11_08/o1_m f_1 2_3m5hlsvs_arc thread=1 sequence=2 archive log filename=/oracle/product/10.2.0/db_1/flash_recovery_area/GDB1/archivelog/2007_11_08/o1_m f_1 3_3m5hlyby_arc thread=1 sequence=3 media recovery_complete, elapsed time: 00:00:01 Finished recover at 08-NOV-07
 RMAN> alter database open resetlogs;
database opened
```

For Oracle 8i

- a. Set ORACLE_SID to your database's System Identifier (SID)
 - \$ export ORACLE_SID=GDB1 (assuming your database's SID is GDB1)
- b. Run Oracle Server Manager (svrmgrl)
 - \$ svrmgrl
- Connect to the target database

SVRMGRL> connect internal

d. Start and mount database

SVRMGRL> start mount;

e. Reapply all transactions from the archived log files

RMAN> recover database using backup controlfile

f. Open database

RMAN> ALTER DATABASE OPEN RESETLOGS;

Oracle 8i Example:



```
$ svrmgrl
     SVRMGRL> connect internal
   SVRMGR> startup mount;
 ORACLE instance started.
ORACLE instance started.
Total System Global Area
Fixed Size
Variable Size
Database Buffers
Redo Buffers
Database mounted.
                                                                                                                                                                                                    95874448 bytes
                                                                                                                                                                                                   64912 bytes
52744192 bytes
40960000 bytes
2105344 bytes
   SVRMGRL> recover database using backup controlfile
 ORA-00279: change 419671 generated at 06/14/03 02:51:49 needed for thread 1
ORA-00289: suggestion : /data/ora815/vin/archive/ARCH0000000225.LOG
ORA-00280: change 419671 for thread 1 is in sequence #225
ORA-00278: log file '/data/ora815/vin/archive/ARCH0000000224.LOG' no longer needed for
   this recovery
Specify log: {<RET>=suggested | filename | AUTO | CANCEL}
   Log applied.
 ORA-00278: log file '/data/ora815/vin/archive/ARCH000000383.LOG' no longer needed for Maranto for control of the control of th
 ORA-7002/06: 100 fire /data/statos/....
this recovery
ORA-00308: cannot open archived log '/data/ora815/vin/archive/ARCH0000000384.LOG'
ORA-27037: unable to obtain file status
Linux Error: 2: No such file or directory
Additional information: 3
 SVRMGR> recover database using backup controlfile until cancel
ORA-00279: change 547222 generated at 06/18/03 19:58:26 needed for thread 1
ORA-00289: suggestion: /data/ora815/vin/archive/ARCH0000000384.LOG
ORA-00280: change 547222 for thread 1 is in sequence #384
Specify log: {<RET>=suggested | filename | AUTO | CANCEL}
   Media recovery cancelled.
     SVRMGR> alter database open resetlogs;
   Statement processed.
```

vi. (Optional) Create Net Service Name and Database Service Listener

To create Net Service Name

Start Net Manager by running the command netmgr

\$ netmgr

- → expand [Oracle Net Configuration]
- → expand [Local]
- → select [Service Naming]
- → click "+" icon on the toolbar
- → Net Service Name Wizard will be launched to guide you through creating a net service name
- → click [File] on the menu bar
- → [Save Network Configuration] on the menu bar

To create Database Service Listener

Start **Net Manager** by running the command **netmgr**

\$ netmar

- → expand [Oracle Net Configuration]
- → expand [Local]
- → expand [Listeners]
- → select [LISTENER]
- → select [Database Services] from combo box
- → click [Add Database]
- ightarrow input Global Database Name and SID
- → click [File] on the menu bar
- → [Save Network Configuration] on the menu bar



9.5 How to restore a single tablespace

Restoring a tablespace required a backup of datafiles consistent with the existing archived logs and control files, as redo will be applied during the restore operation.

Please follow the instructions below to restore a tablespace from Blaze Vault Server.

i. Download the backup files from Blaze Vault Server.

Please refer to the [Quick Start - Backup File] section for information on how to download backup files from Blaze Vault Server.

- ii. Set ORACLE_SID to your database's System Identifier (SID)
 - \$ export ORACLE_SID=GDB1 (assuming your database's SID is GDB1)
- iii. Run SQL Plus and connect to database as SYSDBA

```
$ sqlplus "/ as sysdba"
```

iv. Shutdown database

```
SQL> shutdown immediate
```

v. Put the downloaded tablespace datafiles in place

Datafile names and paths can be found by using the REPORT SCHEMA command.

- a. Set ORACLE_SID to your database's System Identifier (SID)
 - \$ export ORACLE_SID=GDB1 (assuming your database's SID is GDB1)
- b. Run Oracle Recovery Manager (rman) and connect to the target database

```
$ rman target /
```

c. Start and mount database

```
RMAN> startup mount
```

d. List the names of all datafiles and tablespaces

RMAN> report schema;

For example:

```
Report of database schema
File K-bytes
             Tablespace RB segs Datafile Name
        419840 SYSTEM
/oracle/OraHome1/oradata/GDB1/system01.dbf
        204800 UNDOTBS1
2
/oracle/OraHome1/oradata/GDB1/undotbs01.dbf
         20480 CWMLITE
/oracle/OraHome1/oradata/GDB1/cwmlite01.dbf
                                    /oracle/OraHome1/oradata/GDB1/drsys01.dbf
         20480 DRSYS
                            ***
5
        141440 EXAMPLE
/oracle/OraHome1/oradata/GDB1/example01.dbf
                                   /oracle/OraHome1/oradata/GDB1/indx01.dbf
6
         25600 INDX
                           ***
                            ***
                                    /oracle/OraHome1/oradata/GDB1/odm01.dbf
         20480 ODM
                            ***
8
         10240 TOOLS
                                    /oracle/OraHome1/oradata/GDB1/tools01.dbf
         25600 USERS
                            ***
                                    /oracle/OraHome1/oradata/GDB1/users01.dbf
10
                            ***
         39040 XDB
                                    /oracle/OraHome1/oradata/GDB1/xdb01.dbf
```



e. Put all the downloaded backup of datafile/s that constitute the tablespace to the listed location

For example:

```
/obm_restore/Oracle Database
Server/oracle/OraHome1/oradata/GDB1/TS1_datafile1.dbf
/obm_restore/Oracle Database
Server/oracle/OraHome1/oradata/GDB1/TS1_datafile2.dbf
```

/obm_restore/Oracle Database Server/oracle/OraHome1/oradata/GDB1/*TS1_datafile3.dbf*

Move to

/oracle/OraHome1/oradata/GDB1/TS1_datafile1.dbf

/oracle/OraHome1/oradata/GDB1/TS1_datafile2.dbf

/oracle/OraHome1/oradata/GDB1/TS1_datafile3.dbf

vi. Restore tablespace

```
RMAN> recover tablespace TS1; (assuming your tablespace is TS1)
```

If your datafiles consistent with the database, you should see:

```
Oracle 9i/10g Example:

RMAN> recover tablespace TS1;

Starting recover at 19-JUL-07
allocated channel: ORA_DISK_1
channel ORA_DISK_1: sid=156 devtype=DISK

starting media recovery

archive log thread 1 sequence 1 is already on disk as file D:\ORACLE\PRODUCT\10.
2.0\FLASH_RECOVERY_AREA\GDB1\ARCHIVELOG\2007_07 19\01 MF 1 1 39Y98F0H .ARC
archive log thread 1 sequence 2 is already on disk as file_D:\ORACLE\PRODUCT\10.
2.0\FLASH_RECOVERY_AREA\GDB1\ARCHIVELOG\2007_07 19\01 MF 1 2 39Y98JSD .ARC
archive log thread 1 sequence 3 is already on disk as file_D:\ORACLE\PRODUCT\10.
2.0\FLASH_RECOVERY_AREA\GDB1\ARCHIVELOG\2007_07 19\01 MF 1 2 39Y98JSD .ARC
archive log thread 1 sequence 3 is already on disk as file_D:\ORACLE\PRODUCT\10.
2.0\FLASH_RECOVERY_AREA\GDB1\ARCHIVELOG\2007_07 19\01 MF 1 3 39Y9SW4D .ARC
archive log filename=D:\ORACLE\PRODUCT\10.2.0\FLASH_RECOVERY_AREA\GDB1\ARCHIVELOG
G\2007_07 19\01 MF 1 1 39Y9SF0H .ARC thread=1 sequence=1
media recovery complete, elapsed time: 00:00:01
Finished recover at 19-JUL-07
```

If your datafiles does not consistent with the database, you should see:

In this case, you need to find the consistent datafiles in order to restore the tablespace.

If there are archive log missing, you should see:

In this case, you need to find the missing archive log files in order to restore the tablespace.

vii. Open database

RMAN> alter database open;

```
Oracle 9i/10g Example:
$ export ORACLE SID=GDB1
 $ rman target /
 Recovery Manager: Release 9.2.0.1.0 - Production
 Copyright (c) 1995, 2002, Oracle Corporation. All rights reserved.
 connected to target database (not started)
Oracle instance started
database mounted
 Total System Global Area 235999352 bytes
Fixed Size 450680 bytes
Variable Size 201326592 bytes
Database Buffers 33554432 bytes
Redo Buffers 667648 bytes
  MAN> report schema;
using target database control file instead of recovery catalog
Report of database schema
using target database controlfile instead of recovery catalog
Report of database schema
File K-bytes Tablespace RB segs Datafile Name
        10
11
12
13
List of Temporary Files
File Size(MB) Tablespace
                                     Maxsize(MB) Tempfile Name
```



1 20 TEMP 32767 D:\ORACLE\PRODUCT\10.2.0\ORADATA\
GDB1\TEMP01.DBF

RMAN> recover tablespace TS1;

Starting recover at 30-AUG-07
allocated channel: ORA DISK 1
channel ORA_DISK_1: sid=11 devtype=DISK

starting media recovery
media recovery complete

Finished recover at 30-AUG-07

RMAN> alter database open;

database opened



9.6 Export and Import a Database (Logical Backup)

While physical backup of database files permit the full reconstruction of database, logical backup is a useful supplement to physical backup for some purposes. For instance, logical backup using the export and import utilities are the only method that Oracle supports for moving an existing database from one platform to another.

Please follow the instructions below to backup a database:

i. Export the full database to a dump file

\$ exp system/pwd123 FULL=y FILE='/oracle/data.dmp' LOG='/oracle/export.log'
(assuming your system password is pwd123, the name of dump file is /oracle/data.dmp
and the name of log file is /oracle/export.log)

ii. Backup the exported dump file to Blaze Vault Server.

Please refer to the [Section 6.2 Backup files directly to the backup server] for information on how to upload backup files to Blaze Vault Server.

Please follow the instructions below to restore a database:

iii. Download the backup files from Blaze Vault Server.

Please refer to the [Section 7.1 Restore backup files directly from backup server] for information on how to download backup files from Blaze Vault Server.

iv. Import the full database from the downloaded backup of dump file

\$ imp system/pwd123 FULL=y FILE='/oracle/data.dmp' LOG='/oracle/import.log'

(assuming your system password is pwd123, the name of dump file is /oracle/data.dmp and the name of log file is /oracle/import.log)

```
Oracle 9i/10g Example:

$ imp system/pwd123 FULL=y FILE='/oracle/data.dmp' LOG='/oracle/import.log'

Connected to: Oracle Database 10g Enterprise Edition Release 10.2.0.1.0 - Production With the Partitioning, OLAP and Data Mining options

Export file created by EXPORT:V10.02.01 via conventional path import done in WEBMSWIN1252 character set and AL16UTF16 NCHAR character set . importing SYSTEM's objects into SYSTEM
. importing OLAPSYS's objects into SYSMAN
. importing SYSMAN's objects into SYSMAN
. importing SYSTEM's objects into SYSTEM
. importing OLAPSYS's objects into OLAPSYS
```





10 Backup/Restore Microsoft SQL Server 7.0 / 2000 / 2005 / 2008

This chapter will describe in details how to use Blaze Vault to backup your Microsoft SQL Server 7.0 / 2000 / 2005 / 2008 server and how you can restore your Microsoft SQL Server 7.0 / 2000 / 2005 / 2008 server from the backup files.

10.1 Requirements

- i. Blaze Vault must be installed onto the computer running Microsoft SQL Server.
- ii. Data from Microsoft SQL Server will be backed up to a temporary directory before they are sent to Blaze Vault Server. Please make sure you have sufficient space on your computer to store these data when you run the backup job.

10.2 Overview

Blaze Vault will backup your Microsoft SQL Server database(s) by taking the following steps:

- Before running any backup activities, Blaze Vault will run all Pre-Commands of the backup set.
- iv. For each database that is to be backed up, Blaze Vault will issue a database / transaction log backup command to Microsoft SQL Server to backup each database to a Microsoft SQL Server database backup file (*.bak file) and save it in the temporary directory you specified.
- After all *.bak files have been spooled to the temporary directories, Blaze Vault will run all Post-Commands of the backup set.
- vi. Upload all files copied to the temporary directory to Blaze Vault Server.
- vii. Remove temporary files from the temporary directory

10.3 How to backup Microsoft SQL Server database(s)

Please follow the instructions below to backup your Microsoft SQL Server databases using Blaze Vault.

i. Open Blaze Vault

Right click Blaze Vault icon available in the system tray and choose [Open]






ii. Create a backup set


- a. To start setting up backup sets, click the button to open the [Backup Setting] dialog.
- b. On the left panel, press the $\[egin{smallmatrix} \blacksquare \\ \end{array} \]$ button to create a new backup set.
- c. On the dialog, choose [MS SQL Server Backup] as the [Type].




d. Enter a name for your backup set



- e. Enter the Microsoft SQL Server administrator username and password
- f. Select the database(s) you want to backup



g. Set the backup schedule for full database backup and transaction log backup



(Note: You can have more than one schedule in a backup set, i.e. you can perform intra-day transaction log backup by adding more than one daily transaction log backup schedule to your backup set)

h. Set the encryption algorithm, encryption mode and encrypting key for this backup set



(Hint: For maximum security, please select AES (Advanced Encryption Standard) Algorithm, CBC (Cipher Block Chaining) mode and use an encrypting key with more than 8 characters.)

- iii. Run Backup
 - a. Press the [Backup] button on the main page of Blaze Vault dialog.
 - b. Select the backup type (e.g. Complete, Differential, Transaction Log) you would like to perform. Select the backup set you want to run and select [Offsite Backup Server] to

start backing up your files to Blaze Vault Server. If applicable, you can change the In-File Delta Type also.



c. Click [OK] to start backing up your files to Blaze Vault Server.

10.4 How to restore Microsoft SQL Server database(s)

Please follow the instructions below to restore your Microsoft SQL Server databases from Blaze Vault Server.

i. Download the backup files (.bak) from Blaze Vault Server

Please refer to the [Quick Start - Backup File] section for information on how to download backup files from Blaze Vault Server.

ii. Open Microsoft SQL Enterprise Manager

You can open Microsoft SQL Enterprise Manager from [Start Menu] -> [Program] -> [Microsoft SQL Server] -> [Enterprise Manager]

iii. (Optional) Restore "master" database

You need to restore "master" database if you:


- a. are rebuilding all your databases from scratch
- b. have changing any server-wide or database configuration options
- c. have added logins or other login security-related operations.
- d. have created or removed logical backup devices.
- e. have configured the server for distributed queries and remote procedure calls, such as adding linked servers or remote logins.

You do not need to restore your master database if you just want to restore a user database. For more information on Microsoft SQL Server "master" database, please visit http://www.microsoft.com/sql/.

To restore "master" database, please do the following:

- a. Start Microsoft SQL Server in "Single User Mode"
 - 1. Right click your Microsoft SQL Server and select [Properties].





2. Press the [Startup Parameters] button.




3. Add a "-m" parameter to the [Startup Parameters].




4. Restart Microsoft SQL Server.

From [Enterprise Manager], right click your Microsoft SQL Server and select [Stop] and then [Start].









- b. Restore "master" database
 - 1. From [Enterprise Manager] -> [Tools] -> [Restore Database].






- 2. Select [master] in the [Restore as database] drop down list.
- 3. Select the [From device] radio button.
- 4. Press the [Select Devices] button.



5. From the [Choose Restore Devices], press the [Add] button.



6. From the [Choose Restore Destination] panel, press the [...] button to choose your



master backup (*.bak) from your backup files.



- 7. Press the [OK] button, to start restoring the "master" database.
- c. Restart Microsoft SQL Server in "Normal Mode"
 - 1. Remove "-m" parameter from the [Startup Parameters] as in previous step.
 - 2. Restart your Microsoft SQL Server as in previous step.
- iv. (Optional) Restore "model", "msdb" and "distribution" database

You need to restore "model" database if you have changed the database template of your SQL Server.

You need to restore "msdb" database if you have changed the scheduling information or you want to restore the backup and restore history of your databases.

You need to restore "distribution" database if you are running the replication components of SQL Server.

You do not need to restore these databases if you just want to restore a user database. For more information on Microsoft SQL Server "model", "msdb" and "distribution" database, please visit http://www.microsoft.com/sql/.

You need to restore each of these databases one by one. To restore any of these databases, please do the following:


- a. From [Enterprise Manager] -> [Tools] -> [Restore Database].
- b. Select the database to be restored in the [Restore as database] drop down list.
- c. Select the [From device] radio button.
- d. Press the [Select Devices] button.
- e. Press the [...] button to choose your backup files (*.bak) for the database to be restored.
- f. Press the [OK] button.
- v. Restore user database(s)

For each of the database you would like to restore,

- a. From [Enterprise Manager] -> [Tools] -> [Restore Database].
- b. Select the database to be restored in the [Restore as database] drop down list.



c. Select the [Database] radio button.



- From the [Show backups of database] drop down list, select the database to be restored
- e. From the [First backup to restore] drop down list, select the snapshot of the database you would like to restore to.

You can restore your database to the snapshot of your database at any point of the time between the time you did your full backup and the time you did your last subsequent backup.

f. Change the [Restore From] entry

If you backup files (*.bak) are not in the default directory, you need to update the full path to your backup files by pressing the [Properties] button.

- g. Press the [OK] button
- vi. All database(s) restored successfully



11 Backup/Restore Lotus Domino / Notes

This chapter will describe in details how to use Blaze Vault to backup your Lotus Domino server / Notes client 5 / 6 / 6.5 and how you can restore your Lotus Domino server / Notes client 5 / 6 / 6.5 from the backup files.

11.1 Requirements

- i. Blaze Vault must be installed onto the computer running Lotus Domino server / Notes client.
- ii. Data from Lotus Domino server / Notes client will be backed up to a temporary directory before they are sent to Blaze Vault Server. Please make sure you have sufficient disk space on your computer to store these data when you run the backup job.
- Lotus Domino server must runs with archive transaction logging enabled

To set up transaction logging in archive style, please do the following:

- a. Ensure that all databases to be logged reside in the Domino data directory, either at the root or in subdirectories.
- b. From the Domino Administrator, click the Configuration tab.
- c. In the "Use Directory on" field, choose the server's Domino Directory.
- d. Click Server Configuration, and then click Current Server Document.
- e. Click the Transactional Logging tab.
- f. Complete these fields, and then save the document.

Field	Enter
Transactional Logging	Choose Enabled. The default is Disabled.
Log path	Path name location of the transaction log. The default path name is \LOGDIR in the Domino data directory, although it is strongly recommended to store the log on a separate, mirrored device, such as a RAID (Redundant Array of Independent Disks) level 0 or 1 device with a dedicated controller. The separate device should have at least 1GB of disk space for the transaction log. If you are using the device solely for storing the transaction log, set the "Use all available space on log device" field to Yes.
Logging style	Choose Archive. The default is Circular.
Maximum log space	The maximum size, in MB, for the transaction log. Default is 192MB. Maximum is 4096MB (4GB). Domino formats at least 3 and up to 64 log files, depending on the maximum log space you allocate.



Use all available space on log device	Choose one: "Yes" to use all available space on the device for the transaction log. This is recommended if you use a separate device dedicated to storing the log. If you choose "Yes", you don't need to enter a value in the "Maximum log space" field. "No" to use the default or specified value in the "Maximum log space" field.
Automatic fixup of corrupt databases	Choose one: • Enabled (default). If a database is corrupt and Domino cannot use the transaction log to recover it, Domino runs the Fixup task, assigns a new DBIID, and notifies the administrator that a new database backup is required. • Disabled. Domino does not run the Fixup task automatically and notifies the administrator to run the Fixup task with the -J parameter on corrupt logged databases.
Runtime / Restart performance	This field controls how often Domino records a recovery checkpoint in the transaction log, which affects server performance. To record a recovery checkpoint, Domino evaluates each active logged database to determine how many transactions would be necessary to recover each database after a system failure. When Domino completes this evaluation, it: Creates a recovery checkpoint record in the transaction log, listing each open database and the starting point transaction needed for recovery Forces database changes to be saved to disk if they have not been saved already Choose one: Standard (default and recommended). Checkpoints occur regularly. Favor runtime. Domino records fewer checkpoints, which requires fewer system resources and improves server run time performance. Favor restart recovery time. Domino records more checkpoints, which improves restart recovery time because fewer transactions are required for recovery.

Notes:

You can only run transaction log backup if you have transaction logging enabled and you are using archive mode. This command does not apply if you have transaction logging enabled not in archive mode or if transaction logging is not enabled at all. If you try to issue it, you will receive an error message.

11.2 Overview

Blaze Vault will backup your Lotus Domino server / Notes client by taking the following steps:

- i. Run all Pre-Commands of this backup set
- ii. If the backup type to run is [Database Backup type],
 - a. all file(s) / database(s) selected are copied to the temporary directory specified by this backup set



- b. the notes.ini file, if selected, will be copied to the temporary directory
- only filled log extents will be copied to the temporary directory, and the Domino server is notified of their availability for reuse (for Domino server only)
- iii. (for Domino server only) If the backup type to run is [Transaction Log Backup type],
 - a. only filled log extents will be copied to the temporary directory, and the Domino server is notified of their availability for reuse
- iv. Run all Post-Commands of this backup set
- v. Upload all files copied to the temporary directory to Blaze Vault Server
- vi. Remove temporary files from the temporary directory



11.3 How to backup Lotus Domino / Notes database(s) / file(s) on Windows


Please follow the instructions below to backup your Lotus Domino server / Notes client databases / files using Blaze Vault.

i. Open Blaze Vault

Right click Blaze Vault icon available in the system tray and choose [Open]




- ii. Create a backup set
 - b. To start setting up backup sets, click the button to open the [Backup Setting] dialog.
 - c. On the left panel, press the 🖹 button to create a new backup set.
 - d. On the dialog, choose [Lotus Domino Server Backup] (or [Lotus Notes Client Backup] for Lotus Notes) as the [Type].




e. Enter a name for your backup set.






- f. Select the location of the "note.ini" file.
- g. Select the database(s) / file(s) you want to backup



h. Set the backup schedule for Database Backup



- Set the backup schedule for Transaction Log Backup (for Domino server only) (Note: You can have more than one schedule in a backup set, i.e. you can perform intra-day transaction log backup by adding more than one daily transaction log backup schedule to your backup set)
- j. Set the encryption algorithm, encryption mode and encrypting key for this backup set






(Hint: For maximum security, please select AES (Advanced Encryption Standard) Algorithm, CBC (Cipher Block Chaining) mode and use an encrypting key with more than 8 characters.)

iii. Run Backup

- a. Press the [Backup] button on the main page of Blaze Vault dialog.
- b. Select the backup type (e.g. Database, Transaction Log) you would like to perform (for Domino server only). Select the backup set you want to run and select [Offsite Backup Server] to start backing up your files to Blaze Vault Server. If applicable, you can change the In-File Delta Type also.



c. Click [OK] to start backing up your files to Blaze Vault Server.

11.4 How to restore Lotus Domino / Notes database(s) / file(s) on Windows

Please follow the instructions below to restore Lotus Domino server / Notes client database(s) / file(s) from Blaze Vault Server.

- i. Install Lotus Domino server / Notes client back to its original folder (if required)
- ii. Install Blaze Vault



Please refer to the [Installation] section for information on how to install Blaze Vault onto your computer.

- iii. Shutdown Lotus Domino Server
- iv. If you want to perform a full domino restore (restore all databases and files):
 - a. Download the backup files to be restored from Blaze Vault Server and save them back to its original location. It includes "notes.ini", all backup files from the lotus domino data directory and all archived transaction logs
 - b. Modify the "DominoRecover.bat" located under the bin directory of the Blaze Vault installation to reflect your setup. You need to specify the lotus executable directory.

For example change the PROGRAM_DIR to: PROGRAM_DIR=C:\Lotus\Domino

c. Run "DominoRecover.bat" and press 'Y' to continue. For example: C:\program files\obm\bin\DominoRecover.bat

This will run media recovery for all databases (*.nsf and mail.box) found under the Lotus data directory (e.g. C:\Lotus\Domino\Data). You should see something similar to the screen below.

Media Recovery Example: C:\program files\obm\bin>DominoRecover.bat Media Recovery Utility for Lotus Domino 5.0 or above Please make sure that you have done the following: 1. Reinstall Lotus Domino on this computer in the same directory 2. Restore Notes.ini to the Lotus Domino installation directory (e.g. C:\Lotus\Domino) 3. Restore Domino Data directory back to the directory defined in Notes.ini (e.g. C:\Lotus\Domino\Data) 4. Restore all archived transaction logs to the directory defined in Notes.ini (e.g. C:\Lotus\Domino\Data\logdir) Continue ? (Y) or (N) y Running media recovery ... Please wait, creating new transaction logs in directory: C:\logdir\ 102/12/2003 14:39:19 Recovery Manager: Restart Recovery complete. (0/0 databases needed full/partial recovery) Media Recovery Replay (122 MB): 10% 20% 30% 40% 50% 60% 70% 80% 90% 100% 02/12/2003 14:39:22 Recovery Manager: Media Recovery complete for C:\Lotus\Domino\Data\admind.nsf, last update applied. Backup file C:\Lotus\Domino\Data\statrep.nsf, last update applied . Backup file C:\Lotus\Domino\Data\statrep.nsf, last update applied .

- d. All content of all database(s) are now rolled forward to the last committed transaction found in the last archived transaction log.
- e. Restart Lotus Domino server
- v. If you just want to restore a single database:
 - Download the database file to be restored from Blaze Vault Server and save them back to its original location.
 - b. (optional) If you need to perform media recovery on this database, please download all archived transaction logs and save them back to its original location



 Modify the "DominoRecover.bat" located under the bin directory of the Blaze Vault installation to reflect your setup.

For example we will recover the "admin4.nsf" and have restored the file to C:\restore\notesdata, change the tags to:

PROGRAM_DIR=C:\Lotus\Domino
INPUTFILE=C:\restore\notesdata\admin4.nsf
RESTOREDB=C:\Lotus\Domino\Data\admin4.nsf
RECDATE=18/01/2007
RECTIME=00:02

d. Run "DominoRecover.bat".

You should see something similar to the screen below.

```
Media Recovery Example:

C:\program files\obm>DominoRecover.bat
Media Recovery Utility for Lotus Domino 5.0 or above

Running media recovery ...
Restart Analysis (0 MB): 100%
18/01/2007 14:42:15 Recovery Manager: Restart Recovery complete. (0/0 databases needed full/partial recovery)

Media Recovery Replay (122 MB): 10% 20% 30% 40% 50% 60% 70% 80% 90% 100%
18/01/2007 14:42:17 Recovery Manager: Media Recovery complete for C:\Lotus\Domino\data\admin4.nsf, last update applied .

Backup file C:\Lotus\Domino\data\admin4.nsf recovered.

C:\Lotus\Domino>
```

- e. All content of the database are now rolled forward to the last committed transaction found in the last archived transaction log.
- f. Restart Lotus Domino Server

11.5 How to backup Lotus Domino / Notes database(s) / file(s) on Linux

Please make sure that the user running Blaze Vault have sufficient privileges to read and write to the "notesenv" file located in the "bin" subdirectory of where Blaze Vault is installed. This file is used by Blaze Vault to store the location of the domino/notes application executables. e.g. use chmod to set read, write & execute permissions

```
# cd $OBM_HOME/bin
# chmod 777 notesenv
```

Please follow the instructions below to backup your Lotus Domino server / Notes client databases / files using Blaze Vault.

i. Open Blaze Vault by typing the following in a terminal

```
# cd $OBM_HOME
# ./bin/RunOBC.sh
```


- ii. Create a backup set
 - a. To start setting up backup sets, click the button to open the [Backup Setting] dialog.
 - b. On the left panel, press the 🖹 button to create a new backup set.




c. On the dialog, choose [Lotus Domino Server Backup] (or [Lotus Notes Client Backup] for Lotus Notes) as the [Type].



d. Enter a name for your backup set




- e. Select the location of the "note.ini" file. The default path for this will be in the /local/notesdata folder.
- f. Select the database(s) / file(s) you want to backup



- g. Enter a temporary location to store the backup files before they are sent to Blaze Vault Server. Please make sure that the user running Blaze Vault have sufficient privileges to read and write to this location and sufficient space is available.
- h. Set the backup schedule for Database Backup







- Set the backup schedule for Transaction Log Backup (for Domino server only) (Note: You can have more than one schedule in a backup set, i.e. you can perform intra-day transaction log backup by adding more than one daily transaction log backup schedule to your backup set)
- j. Set the encryption algorithm, encryption mode and encrypting key for this backup set



(Hint: For maximum security, please select AES (Advanced Encryption Standard) Algorithm, CBC (Cipher Block Chaining) mode and use an encrypting key with more than 8 characters.)



iii. Run Backup

- a. Press the [Backup] button on the main page of Blaze Vault dialog.
- b. Select the backup type (e.g. Database, Transaction Log) you would like to perform (for Domino server only). Select the backup set you want to run and select [Offsite Backup Server] to start backing up your files to Blaze Vault Server. If applicable, you can change the In-File Delta Type also.



- c. Click [OK] to start backing up your files to Blaze Vault Server.
- d. You should get something similar to the screen shot below.



11.6 How to restore Lotus Domino / Notes database(s) / file(s) on Linux

Please follow the instructions below to restore Lotus Domino server / Notes client database(s) / file(s) from Blaze Vault Server.

- i. Install Lotus Domino server / Notes client back to its original folder (if required)
- ii. Install Blaze Vault

Please refer to the [Installation] section for information on how to install Blaze Vault onto your computer.

- iii. Shutdown Lotus Domino Server
- iv. If you want to perform a full domino restore (restore all databases and files):
 - Download the backup files to be restored from Blaze Vault Server and save them back to its original location. It includes notes.ini, all backup files from the lotus domino data



directory and all archived transaction logs. If you encounter any access problems, please try restoring using the "root" user.

b. Make sure that the owner and group permissions of the restored files are the notes user

For example: # chow n -R notes:notes /local/notesdata

This will assign the owner and group to all files and directories within /local/notesdata.

c. Modify the "DominoRecover.sh" located under the bin directory of the Blaze Vault installation to reflect your setup. You need to specify the data directory and the lotus executable directory.

For example change the DATA_DIR and LOTUS tags to:

DATA_DIR=/local/notesdata LOTUS=/opt/ibm/lotus

- d. Make sure the current user is the notes user before running the "DominoRecover.sh".
- e. Run "DominoRecover.sh" and press 'Y' to continue.

For example: #./usr/local/obm/bin/DominoRecover.sh

This will run media recovery for all databases (*.nsf and mail.box) found under the Lotus data directory (e.g. /local/notesdata). You should see something similar to the screen below.

```
Media Recovery Example:

bash-3.00$ cd /usr/local/obm/bin
bash-3.00$ ./DominoRecover.sh
Media Recovery Utility for Lotus Domino 5.0 or above

Please make sure that you have done the following:
1. Reinstall Lotus Domino on this computer in the same directory
2. Restore Notes.ini to the Lotus Domino installation directory
(e.g. /local/notesdata)
3. Restore Domino Data directory back to the directory defined
in Notes.ini (e.g. /local/notesdata)
4. Restore all archived transaction logs to the directory defined
in Notes.ini (e.g. /local/notesdata/)
Continue ? (Y) or (N) y

Running media recovery ...
directory /local/notesdata// already exists
Please wait, creating new transaction logs in directory: /local/notesdata/logdir/
02/01/2007 11:38:43 AM Recovery Manager: Restart Recovery complete. (0/0
databases needed full/partial recovery)
02/01/2007 11:38:45 AM Recovery Manager: Assigning new DBIID for
/local/notesdata/names.nsf (need new backup for media recovery).
Media Recovery Replay (0 MB): 100%
02/01/2007 11:38:45 AM Recovery Manager: Media Recovery complete for
/local/notesdata/dfc/dfc100.nsf, last update applied .

Backup file /local/notesdata/inotesdata/dfc100.nsf recovered.
Media Recovery Replay (0 MB): 100%
02/01/2007 11:38:46 AM Recovery Manager: Media Recovery complete for
/local/notesdata/help/decsdoc.nsf, last update applied .

Backup file /local/notesdata/iNotes/help70_iwa_en.nsf recovered.
Media Recovery Replay (0 MB): 100%
02/01/2007 11:38:50 AM Recovery Manager: Media Recovery complete for
/local/notesdata/mail/notes.nsf, last update applied .

Backup file /local/notesdata/mail/notes.nsf, last update applied .

Backup file /local/notesdata/mail/notes.nsf, last update applied .

Backup file /local/notesdata/mail/notes.nsf, last update applied .
```

- f. All content of all database(s) are now rolled forward to the last committed transaction found in the last archived transaction log.
- g. Restart Lotus Domino server
- v. If you just want to restore a single database:
 - a. Download the database file to be restored from Blaze Vault Server and save them back to its original location.



- (optional) If you need to perform media recovery on this database, please download all archived transaction logs and save them back to its original location
- Modify the "DominoRecover.sh" located under the bin directory of the Blaze Vault installation to reflect your setup.

For example we will recover the "admin4.nsf" and have restored the file to /restore/local/notesdata, change the tags to:

DATA_DIR=/local/notesdata LOTUS=/opt/ibm/lotus INPUTFILE=/restore/local/notesdata/admin4.nsf RESTOREDB=/local/notesdata/admin4.nsf RECDATE=18/01/2007 RECTIME=22:41

- d. Make sure the current user is the notes user before running the "DominoRecover.sh".
- e. Run "DominoRecover.sh".

You should see something similar to the screen below.

```
Media Recovery Example:

bash-3.00$ cd /usr/local/obm/bin
bash-3.00$ ./DominoRecover.sh
Media Recovery Utility for Lotus Domino 5.0 or above
directory /local/notesdata// already exists
Recovering backup file ...
Restart Analysis (0 MB): 100%
18/01/2007 03:35:56 PM Recovery Manager: Restart Recovery complete. (0/0 databa ses needed full/partial recovery)
Media Recovery Replay (1 MB): 30% 50% 80% 100%
18/01/2007 03:35:57 PM Recovery Manager: Media Recovery complete for /local/res tore/local/notesdata/admin4.nsf, last update applied .

Backup file /local/restore/local/notesdata/admin4.nsf recovered.

Taking database /local/notesdata/admin4.nsf offline ...

Restoring database /local/notesdata/admin4.nsf
from recovered backup file /local/restore/local/notesdata/admin4.nsf
setoring database /local/notesdata/admin4.nsf restored from /local/restore/local/notesdata/admin4.nsf
Bringing database /local/notesdata/admin4.nsf online ...

Program completed successfully.
bash-3.00$
```

- f. All content of the database are now rolled forward to the last committed transaction found in the last archived transaction log.
- g. Restart Lotus Domino Server

12 Backup/Restore Microsoft Exchange Server

This chapter will describe in details how to use Blaze Vault to backup your Microsoft Exchange Server 2000 / 2003 / 2007 and how you can restore your Microsoft Exchange Server 2000 / 2003 / 2007 from the backup files.

12.1 Requirements

- i. Microsoft Exchange Server 2000 with Services Pack 3 and post-SP3 update rollup installed. Please refer to http://www.microsoft.com/exchange/ for more information.
 - Microsoft Exchange Server 2003 or Microsoft Exchange Server 2007.
- Blaze Vault must be installed onto the computer running Microsoft Exchange Server 2000 / 2003 / 2007.
- iii. Data from Microsoft Exchange Server will be backed up to a temporary directory before they are sent to Blaze Vault Server. Please make sure you have sufficient space on your computer to store these data when you run the backup job.

12.2 Overview

A Microsoft Exchange Server 2000/2003/2007 stores its data in Windows Active Directory as well as in its databases. To fully backup a Microsoft Exchange Server 2000/2003/2007, you need to backup the following components:

i. Windows System State

The Windows System State contains the information about your Windows system, including Windows Active Directory. A Microsoft Exchange Server 2000 / 2003 / 2007 stores some of its configuration, e.g. email accounts and mailbox properties, inside Windows Active Directory. It is important that Windows Active Directory is backup properly when backing up a Microsoft Exchange Server.

Active Directory is stored inside a Windows Server running as Windows domain controller. If your Exchange Server is a domain controller, you can simply backup the Windows System State of your Exchange Server. If your Exchange Server is running as a member server, you will need to install another copy of Blaze Vault onto the domain controller to backup the Windows System State of inside the domain controller.

For more information on Active Directory, please refer to http://www.microsoft.com/windows2000/technologies/directory/ad/default.asp

ii. Microsoft Information Store

Exchange Server stores all emails and documents inside its databases, which are grouped together as storage groups inside Microsoft Information Store. It is important that Microsoft Information Store is fully backed up when backing your Exchange Server.

iii. Microsoft Site Replication Service

Microsoft Site Replication Service is installed automatically when exchange server site replication feature is enabled. Microsoft Site Replication stores its runtime and configuration information inside its own database. If you are running your Exchange Server with Site Replication Service enabled, please make sure that you backup the site replication database as well.

iv. Microsoft Key Management Service (Exchange 2000 only)

Similarly, if you have setup your Exchange Server with Key Management Services enabled, please make sure that you backup the key management database as well.

Blaze Vault will backup your Microsoft Exchange Server by taking the following steps:



- v. Run all Pre-Commands of this backup set
- vi. If the backup type to run is [Database Backup type],
 - Windows System State will be backed up to a temporary directory specified in its backup set
 - All exchange database(s) selected are backed up to a temporary directory specified in its backup set
- vii. If the backup type to run is [Transaction Log Backup type],
 - New transaction log extents generated since last backup will be copied to the temporary directory
- viii. Remove transaction log extents backed up from the Exchange Server
- ix. Run all Post-Commands of this backup set
- x. Upload all backup files from the temporary directory to Blaze Vault Server
- xi. Remove temporary files from the temporary directory

12.3 How to backup Microsoft Exchange Server

Please follow the instructions below to backup your Microsoft Exchange Server 2000 / 2003 / 2007 using Blaze Vault:


i. Open Blaze Vault

Right click Blaze Vault icon available in the system tray and choose [Open]




- ii. Create a backup set
 - a. To start setting up backup sets, click the button to open the [Backup Setting] dialog.
 - b. On the left panel, press the $\ lacktriangledown$ button to create a new backup set.
 - c. On the dialog, choose [MS Exchange Server Backup] as the [Type].






- d. Enter a name for your backup set.
- e. Select the database(s) to be backed up.



If this Exchange Server is also a domain controller of this Active Directory, select the [System State] checkbox as well. Otherwise, please install Blaze Vault to the domain controller of this Active Directory and select the [System State] checkbox on that computer

- f. Enter a temporary directory for storing the backup files before they are sent to Blaze Vault Server.
- g. Set the backup schedule for Database Backup.



h. Set the backup schedule for Transaction Log Backup.



(Note: You can have more than one schedule in a backup set, i.e. you can perform intra-day transaction log backup by adding more than one daily transaction log backup schedule to your backup set)

i. Set the encryption algorithm, encryption mode and encrypting key for this backup set.



(Hint: For maximum security, please select AES (Advanced Encryption Standard) Algorithm, CBC (Cipher Block Chaining) mode and use an encrypting key with more than 8 characters.)


iii. Run Backup

- a. Press the [Backup] button on the main page of Blaze Vault dialog.
- b. Select the backup type (e.g. Database, Log Files) you would like to perform. Select the backup set you want to run and select [Offsite Backup Server] to start backing up your files to Blaze Vault Server. If applicable, you can change the In-File Delta Type also.



- c. Click [OK] to start backing up your files to Blaze Vault Server.
- d. You should get something similar to the screen shot below.





12.4 How to restore Microsoft Exchange Server

Please follow the instructions below to restore Microsoft Exchange Server 2000 / 2003 / 2007 from Blaze Vault Server.

i. Prepare the system for your Exchange Server (if required)

Install the original version of Windows and Exchange Server (with the same level of service pack installed as in the original system) back to your computer

ii. Restore Windows Active Directory (if required)

If you have re-installed Windows, please download the Windows System State backup file, named [SystemState.bkf], from Blaze Vault Server and then use [NTBackup.exe] to restore your Windows System State to its backup time from the backup file by following the instructions below:

- a. Run [NTBackup.exe] from [Start] -> [Run]
- b. Press the [Restore Wizard] button and then press the [Next] button
- Press the [Import] button and use the [Browse] button to select the backup file [SystemState.bkf] downloaded
- d. Select the checkbox next to the description that matches your backup file
- e. Press the [Next] button and then the [Finish] button
- iii. Install Blaze Vault (if required)

Please refer to the [Installation] section for information on how to install Blaze Vault onto your computer.

- iv. Startup the [Microsoft Information Store] services from Windows Services
- v. Restore exchange database(s) from backup:



a. Download the database backup files to be restored from the Blaze Vault Server (or find the cached copy available in the temporary directory defined in your backup set) and save them to your hard disk (please make sure the directory structure is the same as it appears on the browser), namely:

```
->[C:]
-->[backup]
---->[ABC]
---->[First Storage Group]
----->[Mailbox Store(ABC)]
----->Priv1.edb
----->Priv1.stm
---->[Public Folder Store(ABC)]
----->Pub1.edb
----->Pub1.edb
```

- b. If the database to be restored exists on your computer already, please dismount it from the services using [Start] -> [Program] -> [Microsoft Exchange] -> [System Manager]
- c. Use [ExchangeRestore.exe] (use [ExRestore2k7.exe] for MS Exchange 2007) from the [bin] directory under the installation directory of Blaze Vault (e.g. C:\Program Files\Blaze Vault\bin\ExchangeRestore.exe) to restore the exchange database(s).

Simply run [ExchangeRestore.exe] to print the usage

d. (Example 1) To restore all databases from backup available in [F:\Backup] to an exchange server named [WIN2000SVR] using the temporary directory [F:\Temp], you can use this command:

E:\Program Files\Blaze Vault\bin> ExchangeRestore DIR="F:\Backup" TEMP="F:\Temp" SERVER="WIN2000SVR"

```
E:\Program Files\Blaze Vault\bin> ExchangeRestore DIR="F:\Backup" TEMP="F:\Temp" SERVER="WIN2000SVR"
```

```
Microsoft Exchange Server 2000/2003 Backup Recovery Utility

[Start] Exchange Server - 'WIN2000SVR'
[Start] Service - 'Microsoft Information Store'
[Start] Storage Group - 'First Storage Group'
[Start] Database - 'Mailbox Store (WIN2000SVR)'
Restoring file 'E:\Program Files\Exchsrvr\mdbdata\priv1.edb' ...
Restoring file 'E:\Program Files\Exchsrvr\mdbdata\priv1.edb' ...
[End] Database - 'Mailbox Store (WIN2000SVR)'
[Start] Database - 'Public Folder Store (WIN2000SVR)'
Restoring file 'E:\Program Files\Exchsrvr\mdbdata\publ.edb' ...
Restoring file 'E:\Program Files\Exchsrvr\mdbdata\publ.edb' ...
[End] Database - 'Public Folder Store (WIN2000SVR)'
[Start] Restoring transaction log - 'First Storage Group\
[End] Database - 'Public Folder Store (WIN2000SVR)'
[Start] Restoring transaction log - 'First Storage Group\E00000B3.log' ...
[End] Restoring Log File 'F:\Temp\restore.tmp\First Storage Group\E00000B4.log' ...
[End] Restoring transaction log - 'First Storage Group\E00000B4.log' ...
[End] Applying transaction log ...
[End] Applying transaction log ...
[End] Storage Group - 'First Storage Group'

[Start] Storage Group - 'SG2'
[Start] Database - 'acct'
[Start] Bestoring transaction log - 'SG2'
Restoring Log File 'F:\Temp\restore.tmp\SG2\E01000072.log' ...
Restoring Log File 'F:\Temp\restore.tmp\SG2\E0100073.log' ...
[End] Patabase - 'acct'
[Start] Restoring transaction log - 'SG2'
[Start] Restoring transaction log - 'SG2'
[Start] Applying transaction log - 'SG2'
[Start] Applying transaction log - 'SG2'
[Start] Applying transaction log ...
[End] Exchange Server - 'WIN2000SVR'

E:\Program Files\Blaze Vault\bin>
```

e. (Example 2) To restore the database named [mail] in storage group [SG5] from backup available in [F:\Backup] to an exchange server named [WIN2000SVR] using the temporary directory [F:\Temp], you can use this command:

E:\Program Files\Blaze Vault\bin> ExchangeRestore DIR="F:\Backup" TEMP="F:\Temp" SERVER="WIN2000SVR" SERVICE="Microsoft Information Store" STORAGE="SG5" DATABASE="mail1"

```
E:\Program Files\Blaze Vault\bin> ExchangeRestore DIR="F:\Backup" TEMP="F:\Temp" SERVER="WIN2000SVR" SERVICE="Microsoft Information Store" STORAGE="SG5" DATABASE="mail"

Microsoft Exchange Server 2000/2003 Backup Recovery Utility

[Start] Storage Group - 'SG5'
[Start] Database - 'mail'
Restoring file 'E:\Program Files\Exchsrvr\SG5\mail.edb' ...
Restoring file 'E:\Program Files\Exchsrvr\SG5\mail.stm' ...
[End] Database - 'mail'
[Start] Restoring transaction log - 'SG5'
Restoring Log File 'F:\Temp\restore.tmp\SG5\E0300012.log' ...
Restoring Log File 'F:\Temp\restore.tmp\SG5\E0300013.log' ...
[End] Restoring transaction log - 'SG5'
[Start] Applying transaction log - 'SG5'
[Start] Applying transaction log ...
[End] Applying transaction log
[End] Storage Group - 'SG5'
E:\Program Files\Blaze Vault\bin>
```

- f. Repeat the same procedure for each database to be restored to the Exchange Server.
- g. You can use [Start] -> [Program] -> [Administrative Tools] -> [Event Viewer] to check if there are any errors generated from the exchange databases restoring activities.
- vi. However, if ExchangeRestore.exe still cannot mount the restored files and returns with strange errors, e.g. bad signature, or null errors, the Exchange server might have incorrectly spooled the backup files in the first place. Please try to mount the restored database and log files manually by the following instructions:
 - In MS Exchange System Manager, dismount both the Mailbox Store and Public Folder Store from the server.
 - Copy all the restored database files to the MDBDATA folder (By default, the MDBDATA folder is located under C:\Program Files\Excgsrvr\)

Mailbox Store:



- priv1.edb
- priv1.stm

Public Folder Store:

- pub1.edb
- pub1.stm
- Run "eseutil /r" to apply the transaction log files to bring the database to a consistent state, e.g.:

```
C:\Program Files\Exchsrvr\MDBDATA> ..\bin\eseutil /r e00
```

The above command will try to bring all the databases handled by the transaction log files starting with "e00" located in "C:\Program Files\Exchsrvr\MDBDATA" into clean shutdown state.

d. Run "eseutil /p" to repair the database files, e.g.:

```
C:\Program Files\Exchsrvr\MDBDATA> ..\bin\eseutil /p priv1.edb
C:\Program Files\Exchsrvr\MDBDATA> ..\bin\eseutil /p pub1.edb
```

- e. Mount both Mailbox Store and Public Folder Store to the Server through the MS Exchange System Manager.
- vii. Completed



13 Backup/Restore Windows System State

This chapter will describe in details how to use Blaze Vault to backup Windows System State and how you can restore your Windows System State from backup.

13.1 Requirements

- i. Microsoft Windows XP Professional / 2003 / Vista
- Blaze Vault must be installed onto the computer containing the system state you want to backup
- iii. Windows system state will be backed up to a temporary file before it is sent to Blaze Vault Server. Please make sure you have sufficient space on your computer to store the temporary file when you run the backup job.

13.2 Overview

Blaze Vault will backup your Microsoft Exchange Server by taking the following steps:


- i. Run all Pre-Commands of this backup set
- ii. Windows System State will be backed up to a temporary directory specified in its backup set
- iii. Run all Post-Commands of this backup set
- iv. Upload the Windows System State backup files from the temporary directory to Blaze Vault Server
- v. Remove the Windows System State temporary backup files from the temporary directory if [Setting] -> [Temporary Directory for storing backup files] is enabled

13.3 How to backup Windows System State

Please follow the instructions below to backup Windows System State using Blaze Vault:

i. Open Blaze Vault


Right click Blaze Vault icon available in the system tray and choose [Open]



- ii. Create a backup set
 - a. To start setting up backup sets, click the 🌋 button to open the [Backup Setting] dialog.




- b. On the left panel, press the \blacksquare button to create a new backup set.
- c. On the dialog, choose [System State Backup] as the [Type].



d. Enter a name for your backup set



e. Set the backup schedule for this backup set






f. Set the encryption algorithm, encryption mode and encrypting key for this backup set



(Hint: For maximum security, please select AES (Advanced Encryption Standard) Algorithm, CBC (Cipher Block Chaining) mode and use an encrypting key with more than 8 characters.)


iii. Run Backup

- a. Press the [Backup] button on the main page of Blaze Vault dialog.
- b. Select the backup set you want to run and select [Offsite Backup Server] to start backing up your files to Blaze Vault Server. If applicable, you can change the In-File Delta Type also.



c. You should get something similar to the screen shot below.





13.4 How to restore Windows System State

Please follow the instructions below to restore Windows System State from Blaze Vault Server.

- i. Install Blaze Vault (if required)
 - Please refer to the [Installation] section for information on how to install Blaze Vault onto your computer.
- Restore the Windows System State Backup File (i.e. SystemState.bkf) from the backup server
- iii. Use [NTBackup.exe] to restore your Windows System State to its backup time from the backup file by following the instructions below:
 - a. Run [NTBackup.exe] from [Start] -> [Run]
 - b. Press the [Restore Wizard] button and then press the [Next] button
 - Press the [Import] button and use the [Browse] button to select the backup file [SystemState.bkf] downloaded
 - d. Select the checkbox next to the description that matches your backup file
 - e. Press the [Next] button and then the [Finish] button
- iv. Completed



14 Backup/Restore Individual Brick Level Backup for Microsoft Exchange Server

14.1 Requirements

- Microsoft Exchange Server 2000 with Services Pack 3 and post-SP3 update rollup installed. Please refer to http://www.microsoft.com/exchange/ for more information.

 Or
 - Microsoft Exchange Server 2003 or Microsoft Exchange Server 2007.
- Blaze Vault must be installed onto the computer running Microsoft Exchange Server 2000 / 2003 / 2007.

14.2 Overview

Brick Level Backup for Microsoft Exchange Server is not designed to fully protect an Exchange server, but to facilitate easy backup and fast restore of individual emails, contacts, calendars, tasks etc. The brick level restore cannot fully recover the Information Store after a disaster. If used, a brick level backup must be utilized in conjunction with full Information Store Backup, in order to fully protect the exchange server.

14.3 Granting Privileges

Brick Level Backup requires "Full Mailbox Access" permission for the user running Blaze Vault. Normally, Blaze Vault can acquire the permission on it's own but if you encounter 'Access Denied' errors you need to manually grant access privileges to the user running Blaze Vault using one of the following instructions below:

For one specific mailbox

Use the following procedure to grant access to an Exchange 2000 / 2003 / 2007 mailbox:

- 1 Start Active Directory Users and Computers.
- 2 On the View menu, ensure that the Advanced Features check box is selected.
- 3 Right-click the user whose mailbox you want to give permissions to and choose Properties.
- 4 On the Exchange Advanced tab, click Mailbox Rights.
- 5 Notice that the Domain Admins and Enterprise Admins have both been given Deny access to Full Mailbox access.
- 6 Click Add, click the user or group who you want to have access to this mailbox, and then click OK.
- 7 Be sure that the user or group is selected in the Name box.
- 8 In the Permissions list, click Allow next to Full Mailbox Access, and then click OK.
- 9 Click Ok all the way out.
- 10 Restart the Microsoft Exchange Information Store.



Note: To perform Exchange 2007 Brick-Level Backup, install the standalone version of MAPI from the Microsoft site. Download Standalone version of MAPI

For mailboxes located within a specific mailbox store

Use the following procedure to grant access to an Exchange 2000 / 2003 / 2007 mailbox found on a specific mailbox store:

- 1 Start Exchange System Manager.
- 2 Drill down to your server object within the appropriate Administrative Group. Expand the server object and find the required mailbox store within the appropriate Storage Group. Right-click it and choose Properties.
- In the Properties window go to the Security tab.
- 4 Click Add, click the user or group who you want to have access to the mailboxes, and then click OK.
- 5 Be sure that the user or group is selected in the Name box.
- 6 In the Permissions list, click Allow next to Full Control, and then click OK.
- 7 Click 'Apply' and 'OK'
- 8 Restart the Microsoft Exchange Information Store.

For mailboxes located within a specific server

- 1 Start Exchange System Manager.
- 2 Drill down to your server object within the appropriate Administrative Group. Right-click it and choose Properties.
- 3 In the Properties window go to the Security tab.
- 4 Click Add, click the user or group who you want to have access to the mailboxes, and then click OK.
- 5 Be sure that the user or group is selected in the Name box.
- 6 In the Permissions list, click Allow next to Full Control, and then click OK.
- 7 Click Ok all the way out.
- 8 Restart the Microsoft Exchange Information Store.


14.4 How to backup Individual Brick Level Backup

Please follow the instructions below to backup all individual items within your Microsoft Exchange Server 2000 / 2003 / 2007 using Blaze Vault:


i. Open Blaze Vault

Right click Blaze Vault icon available in the system tray and choose [Open]







- ii. Create a backup set
 - a. To start setting up backup sets, click the button to open the [Backup Setting] dialog.
 - b. On the left panel, press the 🖹 button to create a new backup set.
 - c. On the dialog, choose [MS Exchange Mail Level Backup] as the [Type].



d. Enter a name for your backup set.




e. Select the email account(s) to backup.




You can drill down to select individual items.




f. Set the backup schedule







g. Set the encryption algorithm, encryption mode and encrypting key for this backup set



(Hint: For maximum security, please select AES (Advanced Encryption Standard) Algorithm, CBC (Cipher Block Chaining) mode and use an encrypting key with more than 8 characters.)


iii. Run Backup

- a. Press the [Backup] button on the main page of Blaze Vault dialog.
- Select the backup set you want to run and select [Offsite Backup Server] to start backing up your files to Blaze Vault Server. If applicable, you can change the In-File Delta Type also.





- c. Click [OK] to start backing up your files to Blaze Vault Server.
- d. You should get something similar to the screen shot below.



14.5 How to restore Individual Brick Level Backup

Please follow the instructions below to restore individual emails, contacts, calendars, tasks etc. from Blaze Vault Server back into your exchange server. Please note that individual brick level can only be restored using the Blaze Vault client.

i. Open Blaze Vault


Right click Blaze Vault icon available in the system tray and choose [Open]



- ii. Open Blaze Vault from the System Tray (see previous sections for details).
- iii. Select the [Restore] button on the left of the main page of Blaze Vault dialog.




- iv. Select the backup set from which you would like files to be restored from the list.
- v. Select the items you want to restore



vi. Press the [Start Restore] button to restore

vii. Restore complete. Please logon to exchange to get the restored items.





15 Backup/Restore System with Microsoft Windows System

Backup

This chapter will describe in details how to use Blaze Vault to backup your Mircosoft Windows Server system and how you can restore them from backup files. This feature only works on Microsoft Windows Vista Business/Enterprise/Ultimate Edition and Windows Server 2008.

15.1 Requirements

- The computer is using either Microsoft Windows Vista Business/Enterprise/Ultimate Edition or Windows Server 2008.
- ii. Blaze Vault must be installed onto the computer.
- iii. You must install the Windows Server Backup, Command-line Tools, and Windows PowerShell items that are available in the Add Features Wizard in Server Manager. This installs the following tools:
 - Windows Server Backup Microsoft Management Console (MMC) snap-in
 - Wbadmin command-line tool
 - Windows Server Backup cmdlets (Windows PowerShell commands)
- iv. System images generated by Windows Server Backup will be backed up to a temporary directory before they are sent to Blaze Vault Server. Please make sure you have sufficient space on your computer to store these data when you run the backup job.

15.2 Overview

Blaze Vault will backup your system by taking the following steps:

- Before running any backup activities, Blaze Vault will run all Pre-Commands of the backup set.
- ii. Blaze Vault will issue a system backup command to backup the volume(s) selected in backup source to a set of files and save it in the [WindowsImageBackup] directory under the temporary directory specified in the backup set settings.
- iii. After all files have been spooled to the [WindowsImageBackup] directories, Blaze Vault will run all Post-Commands of the backup set.
- iv. Upload all file copied to the temporary directory to Blaze Vault Server.


15.3 How to backup system with Microsoft Windows System Backup

Please follow the instructions below to backup your Mircosoft Windwos Server 2008 or Windows Vista Business /Enterprise/Ultimate Edition using Blaze Vault.

i. Open Blaze Vault


Right click Blaze Vault icon available in the system tray and choose [Open].






ii. Create a backup set

- a. To start setting up backup sets, click the button to open the [Backup Setting] dialog.
- b. On the left panel, press the $\ lacktriangledown$ button to create a new backup set.
- c. On the dialog, choose [MS Windows System Backup] as the [Type].






d. Enter a name for your backup set.




e. Select the volume(s) you want to backup.




Note: For Windows Vista, C: will be selected as default and cannot be deselected.

f. Set the backup schedule.






g. Set the encryption algorithm, encryption mode and encrypting key for this backup set.



iii. Run Backup

- a. Press the [Backup] button on the main page of Blaze Vault dialog.
- b. Select the backup set you want to run and select [Offsite Backup Server] to start backing up your files to Blaze Vault Server. If applicable, you can change the In-File

Delta Type also.



c. Click [OK] to start backing up your files to Blaze Vault Server.



15.4 How to restore system with Microsoft Windows System Backup

Please follow the instructions below to restore your Microsoft Windows Server 2008 or Windows Vista Business/Enterprise/Ultimate Edition from Blaze Vault Server.

- i. Download the backup file (Microsoft_Windows_System_Backup) from Blaze Vault Server
 - Please refer to the [Quick Start Backup file] section for information on how to download backup files from Blaze Vault Server.
- ii. For Windows Server 2008, please follow the instructions below to recover volumes with Recovery Wizard:
 - a. From the [Start] menu, click [Administrative Tools], and then click [Windows Server Backup].
 - b. In the [Actions] panel of the snap-in default page, under [Windows Server Backup], click [Recover]. This opens the Recovery Wizard.
 - c. On the [Getting started] page, specify whether you will recover volumes from backups stored on this computer or another computer, and then click [Next].
 - d. If you are recovering volumes from backups stored on another computer, do the following, and then click [Next]:
 - On the [Specify location type] page, specify thata you want to restore from a local drive.
 - On the [Select backup location] page, select the location of the backup from the drop-down list.
 - e. Click [Next] to continue.
 - f. For a recovery either from the local computer or another computer, on the [Select backup date] page, select the date from the calendar and the time from the drop-down list of backup you want to restore from.
 - g. On the [Select recovery type] page, click [Volumes], and then click [Next].
 - h. On the [Select volumes] page, select the check boxes associated with the volumes in the [Source Volume] column that you want to recover. Then, from the associated dropdown list in the [Destination Volume] column, select the location that you wean to recover the volume to. Click [Next].
 - Note: You will receive a message that any data on the desintation volume will be lost when you perform the recovery. Make sure that the destination volume is empty or does nto contain information that you will need later.
 - On the [Confirmation] page, review the details, and then click [Recover] to restore the specified volumes.
 - j. On the [Recovery progress] page, you can view the status of the recovery operation and whether or not it was successfully completed.
 - Note: To recover volumes from a backup using Windows Server Backup, you must be a member of the Backup Operators or Administrators groupp, or you must have been delegated the appropriate authority. As a security best practice, consider using [Run as] to perform this procedure.
- iii. For Windows Server 2008, please follow the instructions below to recover the operating system or a full server with Instsall Windows Wizard:



- a. Insert the Windows Setup disc into the CD or DVD drive and turn on the computer. If needed, press the required key to boot from the disc. The Install Windows Wizard should appear.
- b. Specify language settings, and then click [Next].
- c. Click [Repair your computer].
- d. Setup searched the hard disk drives for an existing Windows installation and then displays the results in [System Recovery Options]. If you are recovering the operating system onto separate hardware, the list should be empty (there should be no operating system on the computer). Click [Next].
- e. On the [System Recovery Options] page, click [Window's Complete PC Restore]. This opens the Window's Complete PC Restore Wizard.
- f. Perform one of the following actions:
 - Click [Use the latest available backup (recommended)] and then click [Next].
 - Click [Restore a different backup] and then click [Next].
- g. If you chose to restore a different backup, please perform one of the following actions on the [Select the location of the backup] page:
 - Click the computer that contains the backup that you want to use, and then click [Next]. Then, on the [Select the backup to restore] page, click the backup that you want to use, and then click [Next].
 - Click [Advanced] to brow se for a backup on the network, and then click [Next].
- h. On the [Choose how to restore the backup] page, do the following optional tasks, and then click [Next]:
 - Select the [Format and repartition disks] check box to delete existing partitions and reformat the destination disks to be the same as the backup. This enables the [Exclude disks] button. Click this button and then select the check boxes associated with any disks that you want to exclude from being formatted and partitioned. The disk that contains the backup that you are using is automatically excluded.

Note: Unless a disk is excluded, data on it can be lost – regardless of whether it was part of the backup or whether it has volumes that are being restored. In [Exclude disks], if you do not see all the disks that are attached to the computer, you might need to install the associated drivers for the storage device.

- Select the [Only restore system disks] check box to perform an operating system –only recovery.
- Click [Install drivers] to install device drivers for the hardware that you are recovering to,
- Click [Advanbced] to specify whether the computer is restarted and the disks are checked for errors immediate after the recovery.
- i. Confirm the details for the restoration, and then click [Finish].
- iv. For Windows Server 2008, you can also recover volumes with the following sub command:

Wbadmin start recovery -version: <VersionIdentifier> -itemtypeVolume - items: <VolumeSToRecover> -backupTarget: <VolumeHostingBackup> - recoveryTarget: <TargetVolumeForRecovery>

 Version Identifier: Specifies the version identifier of the backup to recover in MM/DD/YYYY-HH:MM format. If you do not know the version identifier, type



[wbadmin get versions].

- VolumesToRecover: Specifies a comma-delimited list of volumes.
- VolumesHostingBackup: Specifies the storage location that coantains the backup that you want to recover
- TargetVolumeForReocvery: Specify the volume drive letter of the alternate volume to restore to.

For example,

Wbadmin start recovery -versionL03/31/2009-09:00 -itemType:Volume -itmes:D: -backupTarget:E: -recoveryTarget:F:

- For Windows Vista, please perform a Complete PC Restore within the Windows Recovery Environment:
 - a. Insert Windows Vista DVD into the DVD drive and turn on the computer. You will see that a bootable DVD is inserted.



b. Press any key to boot the computer from the Windows Vista DVD. You should now see a black screen with a white status bar at the bottom stating [Windows is loading files...]. After a while, the status bar will turn completely white and you will see a screen stating that Windows is loading.

Note: It is possible that the DVD came with your computer does not allow you to boot off from it. If this is the case, then your computer manufacturer most likely installed the Windows Recovery Environment directly to a small partition on your hard drive. To access this partition, you would slowly tap the [F8] key on your keyboard after the BIOS information clears from your screen until you see the Windows startup menu. From this menu use your arrow keys to select the option for the Windows Recovery Environment and press the enter key on your keyboard.

 Configure the [Language to install], [Time and currency format], and [Keyboard or input method] options. Then, press the [Next] button.






d. Click [Repair your computer].



e. The [System Recovery Options] dialog box will be shown. Select the Vista installation you would like to repair.





Note: If there are drivers you need to load in order for Vista to access any of your drives or other components, then you should click on the [Load Drivers] button to load them. When ready, press the [Next] button to continue. If the repair process does not detect any problems starting Vista, it will display a list of available recovery tools. If it does detect a problem it will attempt to perform a Startup Repair to automatically fix these problems. Click on the [Cancel] button and select the [View advanced options for system recovery and support] option to see the list of recovery tools.

f. Click on the [Windows Complete PC Restore] option.



g. Complete PC Restore will search your hard drives and DVD media for any saved backup image. If none are found, then a message will papear stating that no backups could be found. On the other hand, if a backup was found in one of your drives or the




inserted media, you will see a screen with the latest backup selected.




h. If the selected backup is the one you wish to restore, press the [Next] button to continue. If there is a differenet backup that you would like to use, select the [Restore a different backup] option and press the [Next] button. This will bring up a screen displaying the list of backups you have created in the past.






i. Select the backup that you would like to restore. Then click on the [Next] button. Compelte PC Restore will now examine your selected backup and see if there is more than one time you backed up your computer to this location. If you have backed up multiple times it will display an entry for each of them.





j. It is advised that you select the most recent snapshot and then press the [Next] button to move on to the next screen.






Note: if you select the [Format and repartition disks] options, Complete PC Restore will repartition and format the hard drive you are restoring to exactly as it was when you made the backup. If you do not choose this method, it will just erase the hard disk and restore the data to it. If you are using the same hard drive that you originally used to backup your computer then you may want to select the option to format and repatition disks. On the other hand, if this is a new hard drive that you have partitioned in a different manner, then you should not select this option in order to keep your current disk configuration. It is implrtant to note that with either option you select all the data on the disk you are restoring ot will be erased. When you are ready to continue, you should click on the [Finish] button.



k. A new window is opened stating that all of your data will be erased. If you want to continue with the restore then you need to put a checkmark in the checkbox labeled [I confirm that I want to erase all existing data and restore the backup] and then press the [OK] button. Complete PC Restore will now restore the backup on your computer.



- When the restore is completed, you will see a message stating that it is complete and it will reboot your computer after a certain amount of time. When your computer reboots, you will now be using the data and configuration from the backup you just restored.
- vi. All volume(s) restored successfully.



16 Backup/Restore Windows System with ShadowProtect

This chapter will describe in details how to use Blaze Vault to backup your Microsoft Windows XP / Vista / 2003 / 2008 system and how you can restore them form the backup files.

16.1 Requirements

- i. Blaze Vault must be installed onto the computer with ShadowProtect installed.
- ii. System images generated by ShadowProtect will be backed up to a temporary directory before they are sent to Blaze Vault Server. Please make sure you have sufficient space on yor computer to store these data when you run the back job.

16.2 Overview

Blaze Vault will backup your system by taking the following steps:


- i. Before running any backup activities, Blaze Vault will run all Pre-Commands of the backup
- ii. For each volume that is to be backed up, Blaze Vault will issue a system backup command to backup each volume to a ShadowProtect backup image file (*.spf and *spi file) and save it in the temporary directory you specified.
- iii. After all image files have been spooled to the temporary directories, Blaze Vault will run all Post-Commands of the backup set.
- iv. Upload all files copied to the temporary directory to Blaze Vault Server.

16.3 How to backup system with ShadowProtect

Please follow the instructions below to backup your System with ShadowProtect using Blaze Vault.


i. Open Blaze Vault

Right click Blaze Vault icon available in the system tray and choose [Open].




- ii. Create a backup set
 - a. To start setting up backup sets, click the button to open the [Backup Setting] dialog.
 - b. On the left panel, press the 🖹 button to create a new backup set.

c. On the dialog, choose [ShadowProtect System Backup] as the [Type].




d. Enter a name for your backup set.




e. Enter the installation path of Shadow Protect.



f. Select the volume(s) you want to backup.




g. Set the backup schedule.






h. Set the encryption algorithm, encryption mode and encrypting key for this backup set.



iii. Run Backup

- a. Press the [Backup] button on the main page of Blaze Vault dialog.
- b. Select the backup type (e.g. Complete, Differential, Incemental) you would like to perform. Select the backup set you want to run and select [Offsite Backup Server] to start backing up your files to Blaze Vault Server. If applicable, you can change the In-File Delta Type also.





c. Click [OK] to start backing up your files to Blaze Vault Server.




16.4 How to restore system with ShadowProtect

Please follow the instructions below to restore your system form Blaze Vault Server.

- Download the backup files (.spf, .spi) from Blaze Vault Server. Please refer to the [Quick Start – Backup file] section for information on how to download backup files form Blaze Vault Server.
- ii. There are two methods you can use to restore volumes. The first method is to boot to the StorageCraft Recovery Environment and perform the restore. This option must be used when restoring the system volume where the operating system resides. The second method is to restore a volume, other than the system volume, while running inside of Windows using the Restore Volume Wizard. This method does not require the machine to be rebooted.

To restore a volume, please do the following:

a. Start ShadowProtect or boot to the StorageCraft Recovery Environment.






b. Start Restore Wizard by clicking the [Restore] button in the left panel of the main screen or clicking on the Restore Wizard from the center panel of the main screen.



- c. Click [Next] to continue.
- d. This will bring up the Backup Image to Restore dialog screen. You will need to locate the image file you wish to restore from a destination location. These destination locations can be a local directory or network share.
 - If the image file you wish to restore is located in a previously defined destination location, then select the destination and locate the backup image set form the list. The next dialog screen will let you select the specific point-in-time associated with the backup image set.
 - If the image file you wish toe restore is not located in a previously defined destination location, you will need to browse to the location of the image file you want to restore.

Note: To restore a backup image that is stored on a network share, you must have the proper credentials to access the file.






- e. This will bring up the Backup Image Dependencies dialog screen. Here you will be provided with all the incremental backup image files associated with the full backup image file you selected. Select a backup image file to view its properties in the right side of the dialog. Image file properties include:
 - Image File Properties volume size, creation time, compression, password protection, comment.
 - Original Partition Information style, number, type, bootable option, starting offset and length.
 - Disk Information disk geometry, disk size and number of the first track sectors. You can also view the disk layout graphically at the bottom of the screen. This represents what the disk looked like at the time of backup.
 - Originating machine the operating system version, the machine name, MAC address and the engine version of ShadowProtect used to create the image file.

By viewing the properties, particularly the information in the image file properties. You will able to best select the backup image file you wish to restore. You can change your selection and review the new selection's image file properties by highlighting the image file in the left side of the dialog screen.






- f. This will bring up the Restore Destination dialog screen. Select the location where you want to restore the backup image. You may also right click on a volume and you will have the following options:
 - Delete Volume This will delete a volume. The deleted volume will become unassigned space on the disk that can be repartition.
 - Set Active –This will set the volume active. Only one partition may be designated as active. By setting a volume active, the computer will boot to the volume.
 - Create an exact primary partition Allows you to define and create a primary partition on the disk. You cannot create more than four (4) primary paritions on the same disk.
 - Create extended partition Allows you to extend a partition and then subdivide this partition in to one or more logical partitions.

Note: Restoring a backup image to a volume overwrites all data currently on the volume.


Note: You must have enough space to restore the backup image. For example, you cannot restore a 4GB backup file with only 1GB of free space.






- g. This will bring up the "Specify the Restoration Options" dialog screen. All of these options are important when restoring the system volume on a computer.
 - Set Parition Acitve This will nake the restored drive the active partition (the drive that the machine boots from).
 - Restore MBR Restore the master boot record. The master boot record is contained in the first sector of the first physical hard drive. The MBR consists of a master boot program and a partition table that describes the disk partitions. The master boot program looks at the partition table to see which primary partition is active. It then starts the boot program from the boot sector of the active partition. You can restore the MBR from the image file that was saved with the backup image or you can restore an original Windows MBR.
 - Restore disk signature Restores the original physical disk signature of the hard drive. Disk. Disk signatures are included in Windows Server 2003, Windows 2000 Advanced Server, and Windows NT Server 4.0 Enterprise Edition (SP3 and later) and are necessary before the hard drive can be used.
 - Restore Disk Hidden Track this will restore the first 63 sectors of a drive. Some boot loader applications require this for the system to boot.





h. This will bring up the Wizard Summary. Review the Restore Wizard Summary and click [Finish] to start restoring the volume.



- You can review the progress of restoring the volume by clicking on the [Volume Restore] tab associated with the restore job.
- iii. All volume(s) restored successfully.



17 Backup/Restore MySQL Server

This chapter will describe in details how to use Blaze Vault to backup your MySQL server and how you can restore your MySQL server from the database backup files.

17.1 Requirements

- i. Blaze Vault must be installed onto the computer running MySQL server.
- ii. Data from MySQL server will be backed up to a temporary directory before they are sent to Blaze Vault Server. Please make sure you have sufficient space on your computer to store these data when you run the backup job.
- iii. There must be a MySQL account can be used to connect from localhost.

Add two new MySQL accounts for Blaze Vault

```
mysql> GRANT ALL PRIVILEGES ON *.* TO 'root'@'localhost'
    -> IDENTIFIED BY 'some_pass';
mysql> GRANT ALL PRIVILEGES ON *.* TO 'root'@'localhost.localdomain'
    -> IDENTIFIED BY 'some_pass';
mysql> FLUSH PRIVILEGES;
```

They are superuser accounts with full privileges to do anything with a password of some_pass.

17.2 Overview

Blaze Vault will backup your MySQL server by taking the following steps:

- i. Run all Pre-Commands of this backup set
- ii. All database(s) (either local or external) selected are backed up to a temporary directory specified in its backup set
- iii. Run all Post-Commands of this backup set
- iv. Upload all backup files from the temporary directory to Blaze Vault Server
- v. Remove temporary files from the temporary directory if [Setting] -> [Temporary Directory for storing backup files] is enabled

17.3 How to backup MySQL server on Windows

Please follow the instructions below to backup your MySQL server using Blaze Vault:


i. Open Blaze Vault

Right click Blaze Vault icon available in the system tray and choose [Open]






- ii. From the Menu, Choose [Backup Set] -> [New] -> [MySQL Backup Set] Create a backup set
 - a. To start setting up backup sets, click the button to open the [Backup Setting] dialog.
 - b. On the left panel, press the 🖹 button to create a new backup set.
 - c. On the dialog, choose [MySQL Backup] as the [Type].




d. Enter a name for your backup set




- e. Enter the root password, the MySQL server TCP/IP port number and the path to MySQL backup utility (mysqldump)
- f. Select the database(s) to be backup






- g. Enter a temporary directory for storing the backup files before they are sent to Blaze Vault Server, e.g. C:\Backup\MySQL
- h. Set the backup schedule for Database Backup



i. Set the encryption algorithm, encryption mode and encrypting key for this backup set



(Hint: For maximum security, please select AES (Advanced Encryption Standard) Algorithm, CBC (Cipher Block Chaining) mode and use an encrypting key with more than 8 characters.)


iii. Run Backup



- a. Press the [Backup] button on the main page of Blaze Vault dialog.
- b. Select the backup set you want to run and select [Offsite Backup Server] to start backing up your files to Blaze Vault Server. If applicable, you can change the In-File Delta Type also.



c. You should get something similar to the screen shot below.



17.4 How to backup MySQL server on Linux (command line mode)

If you want to setup Blaze Vault to backup MySQL server running on Linux using command line mode, please do the followings:

- i. Create a backup account on Blaze Vault Server
- Logon to the web interface of Blaze Vault Server using the backup account created in the previous step (doesn't matter if it is not from the Linux server running the MySQL server to be backed up)
- iii. Create a new backup set by pressing the [Backup Set] -> [Add] button
- iv. Select the [Backup Set] -> [Type] -> [MySQL Database Server] radio button and press the

[Update] button (which can be found at the bottom of the page)

v. Setup all [Backup Set] -> [Database Backup Setting]

Settings	Descriptions
MySQL Username (e.g. root)	A MySQL user account that has backup access to the databases to be backed up (e.g. root). Please refer to the [Requirements] section for details
MySQL Password	Password of the MySQL user account being used
Host	IP address / Hostname of the MySQL Server, e.g. localhost
MySQL Connection TCP/IP Port	TCP/IP port used to access the MySQL Server (default: 3306)
Path to MySQL backup utility (mysqldump)	Full path to where mysqldump can be found (e.g. /usr/bin/mysqldump)
Temporary Spooling Directory	A temporary directory to be used to store all MySQL database dump files before they are uploaded to the backup server
Enable Delete Temp. File	Whether to delete the temporary MySQL database dump files after they are uploaded to the backup server

- vi. Setup the [Backup Set] -> [Backup Source] setting
 - Add an "MySQL" entry to the [Backup Source] if you want to backup all databases under this MySQL Server
 - Add two entries, "MySQL/database1" and "MySQL/database2", to the [Backup Source] if you want to backup both "database1" and "database2" under this MySQL Server
 - (Please use "\" instead of "/" if the MySQL server to be backed up is running on Windows instead of Linux)
- vii. Setup the [Backup Set] -> [Backup Schedule] by pressing the [Add] link next the "Backup Schedule" sub-title
- viii. Install Blaze Vault onto the Linux server running MySQL server (Please refer to the [2.1 Installation of Blaze Vault] section for details. The command line mode installation instructions are available on the web interface)
- ix. Completed

If you have started up the Blaze Vault backup scheduler in the previous step, selected databases will be backed up automatically at scheduled time

17.5 How to restore MySQL server

Please follow the instructions below to restore MySQL server from Blaze Vault Server.

- Download the database backup files to be restored from Blaze Vault Server
 Please refer to the [5.3 Restoring file] section for information on how to download backup files from Blaze Vault Server.
- ii. Restore the database named [db_name] from the database backup file [db_name.sql]:



a. Connect to the MySQL server

(Windows) C:\> mysql (Linux) [root@server ~]# mysql

b. Create the database to be restored

mysql> CREATE DATABASE IF NOT EXISTS db_name

c. Restore the database backup file back into the MySQL server

```
mysql> use db_name ;
mysql> source db_name.sql ;
```

If $db_name.sql$ is not located in the current directory, please specify the full path to the $db_name.sql$ file in the command above.

- iii. Repeat the same procedure for each database to be restored to the MySQL Server.
- iv. Completed

18 Email Reporting

Blaze Vault Server makes use of the email system to keep you informed with the status of your backup activities. Please make sure your contact information within the backup system is correct to receive the reports described in this chapter.

18.1 New User Report

When a new backup account is added to the backup server, a new user report will be delivered to the contact email(s) of the new account. The New User Report contains the following information:


Sample Report		
Blaze Vault Backup Services	Gen	erated at: Tue Aug 12 18:07:04 CST 200
Getting started:	User Setting	
Please follow the instructions available in the installation	Login Name	:NewAccount
wizard to download and install Blaze Vault	Alias	:NewAccount Name
Further Information:	Language	:English
If further assistance is required, please refer to the FAQs.	Contact	:new_account@your-company.com
in further assistance is required, please relet to the FAGS.	Backup Quota	:50M

Key	Description
Login Name	Login name
Password	Password
Alias	Alias
Language	Preferred Language for your backup report
Contact	Email Address that will be used to contact you
Backup Quota	Backup quota
Backup Server	Backup server



18.2 Forgot Password Report

If you have forgotten your password, you can use the [Forgot Password] feature available on the web interface to have your password delivered to you through email. (Please refer to "Retrieve Forgotten Password" section in the next chapter for more information on how to retrieve your forgot password report.) The Forgot Password Report contains the following information:




Key	Description
Login Name	Login name
Password	Password
Alias	Alias
Language	Preferred Language for your backup report
Contact	Email Address that will be used to contact you



18.3 Backup Job Report


For each backup job you have run, a backup job report will be sent to you by email. This report contains a summary for the backup job that was run and a full listing of all files being backed up by the backup job. The backup summary report contains the following information:



Key	Description
Backup Time	The time when the backup job ran
Backup Status	The overall status of the backup job. Normally, you should see "Backup finished successfully" in this field. If you happen to get something else, please consult the attached full report for more information.
New Files	Total number and size of backup files added to your backup set
Updated Files	Total number and size of backup files updated in your backup set
Deleted Files	Total number and size of backup files deleted from your backup set
Moved Files	Total number and size of backup files relocated in your backup set
Login Name	Login name
Alias	Alias
Language	Preferred Language for your backup report
Contact	Email Address that will be used to contact you
Backup Source	All files/directories that will be backed up
Backup Data Size	The total backup data stored in the data area
Retention Area Size	The total backup data stored in the retention area. Old copies of updated or deleted backup files are retained in the retention area for the number of days as specified by the retention policy of the backup set before they are removed from the system.
Backup Quota	Backup Quota
Remaining Quota	Remaining Quota



The full backup report, which contains a full listing of all files backed up by the backup job, is attached to the backup job report email as a zip file. You need to unzip it before you can read the full report.




Key	Description
Backup Set	The name of the backup set
Backup Job	The name of the backup job (which is the start time of the backup job)
Backup Status	The overall status of the backup job. Normally, you should see "Backup finished successfully" in this field. If you happen to get something else, please consult the attached full report for more information.
Backup Time	The time when the backup job ran
Backup Log	All messages logged when running this backup job
New Files	Total number and size of backup files added to your backup set
Updated Files	Total number and size of backup files updated in your backup set
Deleted Files	Total number and size of backup files deleted from your backup set
Moved Files	Total number and size of backup files relocated in your backup set
New File List	Full list of all backup files added to your backup set
Updated File List	Full list of all backup files updated in your backup set
Deleted File List	Full list of all backup files deleted from your backup set
Moved File List	Full list of all backup files relocated in your backup set



18.4 Setting Change Report

After you have updated your user profile or backup setting, a setting change report will be sent to you. This report allows you to track record of the changes that have been made to your backup account.



Key	Description
Login Name	Login name
Alias	Alias
Language	Preferred Language for your backup reports
Contact	Email Address that will be used to contact you
Backup Quota	Backup Quota
Backup Source(s)	All backup sources of the backup set
Backup Schedule(s)	All backup schedules of the backup set
Filter(s)	All backup filters of the backup set
Retention Policy	The retention policy of the backup set
Transfer Size	The transfer block size of the backup set
Pre-Command(s)	All Pre-Command(s) of the backup set
Post-Command(s)	All Post-Command(s) of the backup set



18.5 Inactive User Reminder

You will receive an inactive user reminder in email if your account has been left inactive for the period of 7 days (or the period specified by the system administrator). This is to remain you that you have not been running backup for more 7 days. If you are a free trial user, your account will be removed from the system automatically if the system can track no records of your backup activities in the next 30 days after receiving this report.

Sample Report Inactive User Report Generated at: Tue Aug 12 18:21:45 CST 2008 User Setting Why are you receiving this report? Login Name :NewAccount : NewAccount Name Alias You are receiving this report because this backup account has Language :English been inactive for 30 days. If this account stays inactive for another 30 days, this account will be removed from our Contact :new_account@your-company.com system automatically without further notice. The following is the backup activity of this account: Last Login Time: 2008-08-12 05:07:04 PM Last Backup Time: 2008-08-12 05:02:04 PM If further assistance is required, please refer to the FAQs section.

Key	Description
Login Name	Login name
Alias	Alias
Language	Preferred Language for your backup reports
Contact	Email Address that will be used to contact you
Backup Quota	Backup Quota
Last Login Time	The last time you logon to the backup system
Last Backup Time	The last time you ran a backup job



19 Web Features


Other than the features of Blaze Vault described in the previous chapter, the web interface of Blaze Vault Server provides you access to some additional features that are not available in Blaze Vault. This chapter describes each of these features in details.

19.1 Install Blaze Vault

Before you can use Blaze Vault, you have to download the Blaze Vault installer from the web interface of Blaze Vault Server and install Blaze Vault onto your computer. Please refer to the <u>installation section</u> (Chapter 2) for information on how to install Blaze Vault onto your computer.

19.2 Update User Profile


You can update your user profile by using the [Profile] panel available on the web interface. To change your profile, just make any changes to your profit on the panel shown below and press the [Update] button.



Key	Description
Quota	Backup Quota
Data Area	Total number and size backup files stored in the data area
Retention Area	Total number and size of backup files stored in the retention area
Total Upload	Total number and size of backup files uploaded to the backup server
Total Restore	Total number and size of backup files restored from the backup server
Login Name	Login name
Display Name	Alias of your backup account
Language	Preferred Language for your backup report
Time Zone	Your Time zone
Contact	Email Address that will be used to contact you

19.3 Request Forgotten Password

If you have forgotten your password, you can retrieve it by simply entering your login name or your registered email address on the [Password Request] form and press the [Request] button. Your password will be sent to your registered email address automatically.





19.4 Restore/Delete/Undelete Backup Files


Using the [File Explorer], you can browse through the backup data (both current and previous versions) on Blaze Vault Server. You can select any current backup files to Restore or Delete. You can also select any deleted backup files (in gray) to Undelete.





19.5 Review Backup Jobs


In addition to reviewing your backup activities from the email report and from Blaze Vault, you can also review any of your backup Jobs by using the [Report] panel available on the web interface. To review a backup job, select the required backup job from the [Backup Set] and [Backup Job] drop down lists.



Key	Description
Job Status	The overall status of the backup job. Normally, you should see "Backup finished successfully" in this field. If you happen to get something else, please click the [Detailed Report] images on the page.
Backup Time	The time when the backup job ran
New Files	Total number and size of backup files added to your backup set
Updated Files	Total number and size of backup files updated in your backup set
Deleted Files	Total number and size of backup files deleted from your backup set
Moved Files	Total number and size of backup files relocated in your backup set
Backup Data Size	The total backup data stored in the data area
Retention Area Size	The total backup data stored in the retention area. Old copies of updated or deleted backup files are retained in the retention area for the number of days as specified by the retention policy of the backup set before they are removed from the system.
Total Upload	Total number and size of backup files uploaded to the backup server
Backup Quota	Backup Quota
Remaining Quota	Remaining Quota



You can open the [Full Backup Report] to review all information logged by a backup job by clicking the [Detailed Report] image on the [Report] panel.




Parameter	Description
Backup Set	The name of the backup set
Backup Job	The name of the backup job (which is the start time of the backup job)
Backup Status	The overall status of the backup job.
Backup Time	The time when the backup job ran
Backup Log	All messages logged when running this backup job
New Files	Total number and size of backup files added to your backup set
Updated Files	Total number and size of backup files updated in your backup set
Deleted Files	Total number and size of backup files deleted from your backup set
Moved Files	Total number and size of backup files relocated in your backup set
New File List	Full list of all backup files added to your backup set
Updated File List	Full list of all backup files updated in your backup set
Deleted File List	Full list of all backup files deleted from your backup set
Moved File List	Full list of all backup files relocated in your backup set



19.6 Review Storage Statistics

You can review the amount of data you have stored on the backup server and uploaded to the backup server on each day by opening the [Statistics] panel available on the web interface. To review your storage statistics for a different month, just select the month you are after by selecting from the [Month] drop down list.



Key	Description
Date	The date the following statistics are collected
Data Area	Total number and size of backup files stored in the data area on a particular date
Retention Area	Total number and size of backup files stored in the retention area on a particular date
Uploaded Size	Total number and size of backup files uploaded to the backup server on a particular date
Total Storage	Total number and size of backup files stored under your backup account on a particular date



20 Further Information

20.1 FAQs

Please see if your question has already been answered in our FAQs available on our website.

20.2 Contact Us

You can find our contact information by following instructions below.

- i. Open Blaze Vault from the system tray
- ii. Click the 🎐 from the top menu
- iii. Contact us by using the information shown in the [About] dialog box

